

---

# **Amazon Virtual Private Cloud**

## **Network Administrator Guide**

**API Version 2011-07-15**



# Amazon Virtual Private Cloud: Network Administrator Guide

Copyright © 2012 Amazon Web Services LLC or its affiliates. All rights reserved.

Welcome .....	1
The Amazon VPC Customer Gateway .....	2
Example: Cisco IOS Device .....	12
Example: Juniper JunOS Device .....	23
Example: Juniper ScreenOS Device .....	34
Example: Yamaha Device .....	44
Example: Generic Customer Gateway .....	53
Troubleshooting .....	61
Troubleshooting Cisco IOS Customer Gateway Connectivity .....	61
Troubleshooting Juniper JunOS Customer Gateway Connectivity .....	66
Troubleshooting Juniper ScreenOS Customer Gateway Connectivity .....	69
Troubleshooting Yamaha Customer Gateway Connectivity .....	72
Troubleshooting Generic Device Customer Gateway Connectivity .....	75
Document History .....	77

# Welcome

---

Welcome to the *Amazon Virtual Private Cloud Network Administrator Guide*. This guide is only for Amazon VPC customers who plan to use an IPsec hardware VPN with their VPC. The guide helps you configure your Amazon VPC customer gateway, which is the VPN device on your side of the VPN connection.

The VPN connection lets you bridge your VPC and IT infrastructure, and extend your existing security and management policies to your VPC instances as if they were running within your infrastructure.

# The Amazon VPC Customer Gateway

---

## Topics

- [Your Role \(p. 2\)](#)
- [What Is a Customer Gateway? \(p. 45\)](#)
- [Summary of What You Need to Do \(p. 4\)](#)
- [Four Main Parts to Customer Gateway Configuration \(p. 5\)](#)
- [AWS VPN CloudHub and Redundant Customer Gateways \(p. 6\)](#)
- [Configuring Multiple VPN Connections to Your Amazon VPC \(p. 6\)](#)
- [Customer Gateway Devices We've Tested \(p. 8\)](#)
- [Requirements for Your Customer Gateway \(p. 8\)](#)
- [If You Have a Firewall Between the Internet and Your Customer Gateway \(p. 10\)](#)

## Your Role

Throughout this guide, we refer to your company's *integration team*, which is the person (or persons) at your company working to integrate your infrastructure with Amazon VPC. This team might consist of just you, or might not include you at all, depending on how your company allocates network engineering resources. The important thing to know is that someone at your company must use the [AWS Management Console](#) to get the information you need to configure your customer gateway, and someone must actually configure the customer gateway. Your company might have a separate team for each task (an *integration team* that uses the AWS Management Console, and a separate network engineering group that has access to network devices and who configures the customer gateway). Or your company might have a single person who does both tasks, or some other arrangement entirely. This guide assumes the first scenario, and that you're someone in the network engineering group who will receive information from your company's integration team so you can then configure the customer gateway device.

## What Is a Customer Gateway?

Your company has decided to use an optional Amazon VPC *VPN connection* that links your data center (or network, etc.) to your Amazon VPC *virtual private cloud* (VPC). A *customer gateway* is the anchor on

**Amazon Virtual Private Cloud Network Administrator  
Guide  
What Is a Customer Gateway?**


---

your side of that connection. It can be a physical or software appliance. The anchor on the AWS side of the VPN connection is called a *virtual private gateway*. The following diagram shows your network, the customer gateway, the VPN connection that goes to the virtual private gateway, and the VPC. There are two lines between the customer gateway and virtual private gateway because the VPN connection consists of *two tunnels*. We chose this design to provide increased availability for the Amazon VPC service. If there's a device failure within AWS, your VPN connection will automatically fail over to the second tunnel so your access isn't interrupted. When you configure your customer gateway, it's important you configure *both* tunnels.



**Note**


From time to time, AWS will perform routine maintenance on the Virtual Private Gateway. This maintenance may disable one of the two tunnels of your VPN connection for a brief period of time. Your VPN connection will automatically fail over to the second tunnel while this maintenance is performed. To ensure uninterrupted service, it's important that you configure both tunnels.



## Summary of What You Need to Do

The overall process of setting up the VPN connection is covered in the [Amazon Virtual Private Cloud User Guide](#). One task in the process is to configure the customer gateway. The following table summarizes what you need to do to configure the customer gateway.

### Process for Configuring the Customer Gateway

1	Designate an appliance to act as your Amazon VPC customer gateway (for more information, see <a href="#">Customer Gateway Devices We've Tested (p. 8)</a> and <a href="#">Requirements for Your Customer Gateway (p. 8)</a> ).
2	<p>Determine the following information about the customer gateway:</p> <ul style="list-style-type: none"><li>• The vendor (e.g., Cisco Systems), the platform (e.g., ISR Series Routers), and the software version (e.g., IOS 12.4)</li><li>• The Internet-routable IP address for the external interface (the address must be static and can't be behind a device performing network address translation (NAT))</li></ul> <p> <b>Note</b></p> <p>We assume the BGP ASN for the customer gateway is 65000.</p>
3	Give the preceding information to your integration team, who will create your VPN connection using the <a href="#">AWS Management Console</a> . The team will obtain information you need in order to configure the customer gateway.
4	Get this configuration information from the team.
5	Configure your customer gateway using the information from the team.
6	Notify your integration team when you're done configuring the customer gateway so they can move forward with their work.



#### Note

You may create additional VPN connections to other VPCs using the same customer gateway appliance, however, each VPN connection will require a separate public IP address on the customer gateway.

## Determining Your Network Information

The first task for your integration team is to determine the set of information in the following table. The table includes example values for some of the items. You can use the example values or determine real values. You must obtain real values for all the other items.



#### Tip

You can print the table and fill in the values you plan to use in the column on the far right.

**Amazon Virtual Private Cloud Network Administrator  
Guide  
Four Main Parts to Customer Gateway Configuration**

Item	How Used	Comments	Your Value
VPC CIDR block	Used in customer gateway configuration	Example: 10.0.0.0/16	Value:
Subnet #1 CIDR block (can be same as the VPC's CIDR block)		Example: 10.0.1.0/24	Value:
Subnet #2 CIDR block (optional)		Example: 10.0.2.0/24	Value:
Subnet #N CIDR block (optional)		None	Value:
Type of customer gateway (for example, Cisco ISR, Juniper J-Series, Juniper SSG, or other)	Used in an API call to specify how to format the returned information that you use to configure the customer gateway		Value:
Internet-routable IP address (static) of the customer gateway's external interface	Used in customer gateway configuration (it's referred to as YOUR_UPLINK_ADDRESS)	The value must be static and can't be behind a device performing network address translation (NAT).	Value:
Border Gateway Protocol (BGP) Autonomous System Number (ASN) of the customer gateway	Used in customer gateway configuration (it's referred to as YOUR_BGP_ASN)	You can use an existing ASN assigned to your network. If you don't have one, you can use a private ASN (in the 64512–65534 range). For more information about ASNs, go to the <a href="#">Wikipedia article</a> .	Value:






**Note**

If you have a firewall between your customer gateway and the Internet, see [If You Have a Firewall Between the Internet and Your Customer Gateway](#) (p. 10).

## Four Main Parts to Customer Gateway Configuration

There are four main parts to the configuration of your customer gateway. Throughout this guide, we use a special symbol for each of these parts to help you understand what you need to do. The following table shows the four parts and the corresponding symbols.

<b>IKE</b>	IKE Security Association (required to exchange keys used to establish the IPsec security association)
------------	---

 IPsec	IPsec Security Association (handles the tunnel's encryption, authentication, etc.)
 Tunnel	Tunnel interface (receives traffic going to and from the tunnel)
 BGP	BGP peering (exchanges routes between the customer gateway and the virtual private gateway)

## AWS VPN CloudHub and Redundant Customer Gateways

You can establish multiple VPN connections to a single virtual private gateway from multiple customer gateways. This configuration can be used in different ways--you can have redundant customer gateways between your data center and your VPC or you can have multiple locations connected to the AWS VPN CloudHub.

In the redundant customer gateways configuration, each customer gateway advertises the same prefix (e.g. 0.0.0.0/0) to the virtual private gateway. The gateways will be used in an active/active mode, but if one customer gateway fails, the virtual private gateway will direct all traffic to the working customer gateway.

The AWS VPN CloudHub configuration enables multiple sites to access your VPC or securely access each other using a simple hub-and-spoke model. You configure each customer gateway to advertise a site-specific prefix (e.g., 10.0.0.0/24, 10.0.1.0/24) to the virtual private gateway. The virtual private gateway will route traffic to the appropriate site and advertise the reachability of one site to all other sites.

To configure the AWS VPN CloudHub, you use the AWS Management Console to create multiple customer gateways, each with the unique public IP address of the gateway and a unique autonomous system number (ASN). Then create a VPN Connection from each customer gateway to a common VPN gateway. Use the instructions that follow to configure each customer gateway to connect to the virtual private gateway.

To enable instances in your Virtual Private Cloud to reach the virtual private gateway (and then to your customer gateways), you must configure routes in your VPC routing tables. For complete instructions, see the [Amazon Virtual Private Cloud User Guide](#). For AWS VPN CloudHub use cases, you can configure an aggregate route in your VPC routing table (e.g., 10.0.0.0/16) and use more specific prefixes between customer gateways and the virtual private gateway.

## Configuring Multiple VPN Connections to Your Amazon VPC

You can create up to ten VPN connections for your Amazon Virtual Private Cloud (Amazon VPC). You can use multiple VPN connections to link your remote offices to the same VPC. For example, if you have offices in Los Angeles, Tokyo, New York, and London, you can link each of these offices to your VPC. You can also use multiple VPN connections to establish redundant customer gateways from a single location.



### Note

If you need more than ten VPN connections, complete the [Request to Increase Amazon VPC Limits](#) form to request an increased limit.

## Amazon Virtual Private Cloud Network Administrator Guide Configuring Multiple VPN Connections to Your Amazon VPC

---

When you create multiple VPN connections, the Amazon VPC virtual private gateway sends network traffic to the appropriate VPN connection by using Border Gateway Protocol (BGP) route advertisements sent by each customer gateway.

When you have a customer gateway at multiple geographic locations, each customer gateway should advertise a unique set of IP ranges specific to the location. When you establish redundant customer gateways at a single location, both gateways should advertise the same IP ranges.

The Amazon VPC virtual private gateway receives routing information from all customer gateways and calculates the set of preferred paths using the BGP best path selection algorithm. The rules of that algorithm, as it applies to VPC, are:

1. A more specific IP prefix is preferred. (For example, 10.0.0.0/24 will be preferred over 10.0.0.0/16.)
2. When the prefixes are the same, the AS PATH is compared and the prefix with the shortest AS PATH is preferred. Alternatively, you can prepend AS\_PATH, so that the path is less preferred.
3. When the AS PATHs are the same length, the path origin is compared. Prefixes with an Interior Gateway Protocol (IGP) origin are preferred to Exterior Gateway Protocol (EGP) origins, which are preferred to unknown origins.
4. When the origins are the same, the multi-exit discriminator (MED) values are compared. The prefix with the lowest MED is preferred.
5. When the MEDs are the same, the router IDs of the advertising routes are compared. The lowest router ID is preferred.
6. When the router IDs are the same, the BGP peer IP addresses are compared. The lowest peer IP address is preferred.

For example, assume New York and London have different, location-specific prefixes and advertise only the prefix specific to the location. In this case, rule 1 applies, and the virtual private gateway directs traffic to the appropriate location.

Alternatively, assume New York and London share a common prefix and that prefix is advertised from both locations. However, your customer gateway in New York sets the MED to 100, and your London customer gateway sets the MED to 200. Here, rule 5 applies, and the virtual private gateway sends traffic to New York. If the New York router is unavailable, traffic will be re-routed to London.

The following diagram shows the configuration of multiple VPNs.

## Customer Gateway Devices We've Tested

Your customer gateway can be a physical or software appliance.

Following are the devices we've confirmed for customer gateways with Amazon VPC:

- Cisco Integrated Services routers running Cisco IOS 12.4 (or later) software
- Juniper J-Series routers running JunOS 9.5 (or later) software
- Juniper SSG running ScreenOS 6.1, or 6.2 (or later) software
- Juniper ISG running ScreenOS 6.1, or 6.2 (or later) software
- Yamaha RT107e, RTX1200, RTX1500, RTX3000 and SRT100 routers

This guide presents information about how to configure the above types of devices. If you have one of these devices, but configure it for IPsec in a different way than presented in this guide, feel free to alter our suggested configuration to match your particular standards.



## Requirements for Your Customer Gateway

If you have a device that isn't in the preceding list of tested devices, this section describes the requirements the device must meet for you to use it with Amazon VPC. The following table lists the requirement the customer gateway must adhere to, the related RFC (for reference), and comments about the requirement. For an example of the configuration information if your device isn't one of the tested Cisco or Juniper devices, see [Example: Generic Customer Gateway \(p. 53\)](#).

To provide context for the following requirements, think of each VPN connection as consisting of two separate tunnels. Each tunnel contains an IKE Security Association, an IPsec Security Association, and a BGP Peering.

Requirement	RFC	Comments
Establish IKE Security Association using Pre-Shared Keys <b>IKE</b>	<a href="#">RFC 2409</a>	The IKE Security Association is established first between the virtual private gateway and customer gateway using the Pre-Shared Key as the authenticator. Upon establishment, IKE negotiates an ephemeral key to secure future IKE messages. Proper establishment of an IKE Security Association requires complete agreement among the parameters, including encryption and authentication parameters.
Establish IPsec Security Associations in Tunnel mode <b>IPsec</b>	<a href="#">RFC 4301</a>	Using the IKE ephemeral key, keys are established between the virtual private gateway and customer gateway to form an IPsec Security Association (SA). Traffic between gateways is encrypted and decrypted using this SA. The ephemeral keys used to encrypt traffic within the IPsec SA are automatically rotated by IKE on a regular basis to ensure confidentiality of communications.
Utilize the AES 128-bit encryption function	<a href="#">RFC 3602</a>	This encryption function is used to ensure privacy among both IKE and IPsec Security Associations.
Utilize the SHA-1 hashing function	<a href="#">RFC 2404</a>	This hashing function is used to authenticate both IKE and IPsec Security Associations.

**Amazon Virtual Private Cloud Network Administrator  
Guide  
Requirements for Your Customer Gateway**

Requirement	RFC	Comments
Utilize Diffie-Hellman Perfect Forward Secrecy in "Group 2" mode	<a href="#">RFC 2409</a>	IKE uses Diffie-Hellman to establish ephemeral keys to secure all communication between customer gateways and VPN gateways.
Utilize IPsec Dead Peer Detection	<a href="#">RFC 3706</a>	The use of Dead Peer Detection enables the VPN devices to rapidly identify when a network condition prevents delivery of packets across the Internet. When this occurs, the gateways delete the Security Associations and attempt to create new associations. During this process, the alternate IPsec tunnel is utilized if possible.
Bind tunnel to logical interface (route-based VPN) 	None	Your gateway must support the ability to bind the IPsec tunnel to a logical interface. The logical interface contains an IP address used to establish BGP peering to the virtual private gateway. This logical interface should perform no additional encapsulation (e.g., GRE, IP in IP). Your interface should be set to a 1436 byte Maximum Transmission Unit (MTU). An MTU up to 1500 bytes is supported.
Fragment IP packets before encryption	<a href="#">RFC 4459</a>	When packets are too large to be transmitted, they must be fragmented. We will not reassemble fragmented encrypted packets. Therefore, your VPN device must fragment packets <i>before</i> encapsulating with the VPN headers. The fragments are individually transmitted to the remote host, which reassembles them. For more information about fragmentation, go to <a href="#">the Wikipedia article on IP fragmentation</a> .
Establish Border Gateway Protocol (BGP) peerings 	<a href="#">RFC 4271</a>	BGP is used to exchange routes between the customer gateway and virtual private gateway. All BGP traffic is encrypted and transmitted via the IPsec Security Association. BGP is required for both gateways to exchange the IP prefixes reachable via the IPsec SA.

We recommend you use the techniques listed in the following table to minimize problems related to the amount of data that can be transmitted through the IPsec tunnel. Because the connection encapsulates packets with additional network headers (including IPsec), the amount of data that can be transmitted in a single packet is reduced.

Technique	RFC	Comments
Adjust the maximum segment size of TCP packets entering the VPN tunnel	<a href="#">RFC 4459</a>	TCP packets are often the most prevalent type of packet across IPsec tunnels. Some gateways have the ability to change the TCP Maximum Segment Size parameter. This causes the TCP endpoints (clients, servers) to reduce the amount of data sent with each packet. This is an ideal approach, as the packets arriving at the VPN devices are small enough to be encapsulated and transmitted.

**Amazon Virtual Private Cloud Network Administrator  
Guide  
If You Have a Firewall Between the Internet and Your  
Customer Gateway**

Technique	RFC	Comments
Reset the "Don't Fragment" flag on packets	<a href="#">RFC 791</a>	Some packets carry a flag, known as the <i>Don't Fragment (DF) flag</i> , that indicates that the packet should not be fragmented. If the packets carry the flag, the gateways generate an ICMP Path MTU Exceeded message. In some cases, applications do not contain adequate mechanisms for processing these ICMP messages and reducing the amount of data transmitted in each packet. Some VPN devices have the ability to override the DF flag and fragment packets unconditionally as required. If your customer gateway has this ability, we recommend you use it as appropriate.

## If You Have a Firewall Between the Internet and Your Customer Gateway

To use this service, you must have an Internet-routable IP address to use as the endpoint for the IPsec tunnels connecting your customer gateway to the virtual private gateway. If a firewall is in place between the Internet and your gateway, the rules in the following tables must be in place to establish the IPsec tunnels. The virtual private gateway addresses are in the configuration information that you'll get from the integration team.

### **Inbound (from the Internet)**

Input Rule I1	Source IP: Virtual Private Gateway 1, Dest IP: Customer Gateway, Protocol: UDP, Source Port: 500, Destination Port: 500
Input Rule I2	Source IP: Virtual Private Gateway 2, Dest IP: Customer Gateway, Protocol: UDP, Source Port: 500, Destination Port: 500
Input Rule I3	Source IP: Virtual Private Gateway 1, Dest IP: Customer Gateway, Protocol: IP 50 (ESP)
Input Rule I4	Source IP: Virtual Private Gateway 2, Dest IP: Customer Gateway, Protocol: IP 50 (ESP)

### **Outbound (to the Internet)**

Output Rule O1	Source IP: Customer Gateway, Dest IP: Virtual Private Gateway 1, Protocol: UDP, Source Port: 500, Destination Port: 500
Output Rule O2	Source IP: Customer Gateway, Dest IP: Virtual Private Gateway 2, Protocol: UDP, Source Port: 500, Destination Port: 500
Output Rule O3	Source IP: Customer Gateway, Dest IP: Virtual Private Gateway 1, Protocol: IP 50 (ESP)
Output Rule O4	Source IP: Customer Gateway, Dest IP: Virtual Private Gateway 2, Protocol: IP 50 (ESP)

**Amazon Virtual Private Cloud Network Administrator  
Guide  
If You Have a Firewall Between the Internet and Your  
Customer Gateway**

---

Rules I1, I2, O1, and O2 enable the transmission of IKE packets. Rules I3, I4, O3, and O4 enable the transmission of IPsec packets containing the encrypted network traffic.

## Example: Cisco IOS Device

---

### Topics


- [A High-Level View of the Customer Gateway \(p. 45\)](#)
- [A Detailed View of the Customer Gateway and an Example Configuration \(p. 14\)](#)
- [How to Test the Customer Gateway Configuration \(p. 21\)](#)

This section shows an example of the configuration information your integration team gives you if your customer gateway is a Cisco Integrated Services router running Cisco IOS 12.4 (or later) software.

Two diagrams accompany the example configuration: The first diagram shows the high-level layout of the customer gateway, the second diagram supplies details that match the example configuration. You should take the real configuration information that your integration team gives you and apply it to your customer gateway.

## A High-Level View of the Customer Gateway

The following diagram shows the general details of your customer gateway. Note that the VPN connection consists of two separate tunnels: *Tunnel1* and *Tunnel2*. Two redundant tunnels provide an increased availability in the case of a device failure.



## A Detailed View of the Customer Gateway and an Example Configuration

The diagram in this section gives you a detailed illustration of an example Cisco IOS customer gateway. After the diagram is a corresponding example of the configuration information your integration team should give you. The example configuration contains a set of information for each of the two tunnels you must configure.

In addition, the example configuration refers to these items that you must provide:

- **YOUR\_UPLINK\_ADDRESS**—The IP address for the Internet-routable external interface on the customer gateway (which must be static and can't be behind a device performing NAT)
- **YOUR\_BGP\_ASN**—The customer gateway's BGP ASN (we use 65000 by default)


The example configuration includes several dummy values to help you understand how configuration works. For example, we give dummy values for the VPN connection ID (44a8938f), Virtual Private Gateway ID (8db04f81), the IP addresses (e.g., 72.21.209.\*, 169.254.255.\*), and the remote ASN (7224). The actual configuration information you get will replace the dummy values with real values.

In addition to the configuration changes, you must:

- Configure the outside interface
- Configure the tunnel interface IDs (referred to as Tunnel1 and Tunnel2 in the example configuration)
- Ensure that the Crypto ISAKMP Policy Sequence number is unique
- Ensure that the Crypto IPsec Transform Set and the Crypto ISAKMP Policy Sequence are harmonious with any other IPsec tunnels configured on the device
- Configure all internal routing (getting traffic between the customer gateway and your local network)

In the following diagram and example configuration the items highlighted in red *italic* need to be replaced with values that apply to your own particular situation.

**Amazon Virtual Private Cloud Network Administrator  
Guide**  
**A Detailed View of the Customer Gateway and an  
Example Configuration**



**Important**

The following configuration information is an example of what your integration team provides you. Many of the values in the following example will be different from the actual configuration information that you receive. You must use the actual values and not the example values shown here, or your implementation will fail.

```
! Amazon Web Services
! Virtual Private Cloud

! AWS utilizes unique identifiers to manipulate the configuration of
! a VPN Connection. Each VPN Connection is assigned an identifier
! and is associated with two other identifiers, namely the
! Customer Gateway Identifier and Virtual Private Gateway Identifier.
!
! Your VPN Connection ID           : vpn-44a8938f
! Your Virtual Private Gateway ID  : vgw-8db04f81
! Your Customer Gateway ID        : cgw-b4dc3961
!
!
! This configuration consists of two tunnels. Both tunnels must be
! configured on your Customer Gateway.
!
! -----
! IPsec Tunnel #1
! -----
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

**IKE**

```
! #1: Internet Key Exchange (IKE) Configuration
!
! A policy is established for the supported ISAKMP encryption,
! authentication, Diffie-Hellman, lifetime, and key parameters.
!
! Note that there are a global list of ISAKMP policies, each identified by
! sequence number. This policy is defined as #200, which may conflict with
! an existing policy using the same number. If so, we recommend changing
! the sequence number to avoid conflicts.
!
crypto isakmp policy 200
  encryption aes 128
  authentication pre-share
  group 2
  lifetime 28800
  hash sha
exit

! The ISAKMP keyring stores the Pre Shared Key used to authenticate the
! tunnel endpoints.
!
crypto keyring keyring-vpn-44a8938f-0
  pre-shared-key address 72.21.209.225 key plain-text-password1
exit

! An ISAKMP profile is used to associate the keyring with the particular
! endpoint.
!
crypto isakmp profile isakmp-vpn-44a8938f-0
  match identity address 72.21.209.225
  keyring keyring-vpn-44a8938f-0
exit
```

**IPsec**

```
! #2: IPsec Configuration
!
! The IPsec transform set defines the encryption, authentication, and IPsec
! mode parameters.
!
crypto ipsec transform-set ipsec-prop-vpn-44a8938f-0 esp-aes 128 esp-sha-hmac

  mode tunnel
exit

! The IPsec profile references the IPsec transform set and further defines
! the Diffie-Hellman group and security association lifetime.
!
crypto ipsec profile ipsec-vpn-44a8938f-0
  set pfs group2
  set security-association lifetime seconds 3600
  set transform-set ipsec-prop-vpn-44a8938f-0
exit

! Additional parameters of the IPsec configuration are set here. Note that
! these parameters are global and therefore impact other IPsec
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
! associations.
! This option instructs the router to clear the "Don't Fragment"
! bit from packets that carry this bit and yet must be fragmented, enabling
! them to be fragmented.
!
crypto ipsec df-bit clear

! This option enables IPsec Dead Peer Detection, which causes periodic
! messages to be sent to ensure a Security Association remains operational.
!
crypto isakmp keepalive 10 10 on-demand

! This configures the gateway's window for accepting out of order
! IPsec packets. A larger window can be helpful if too many packets
! are dropped due to reordering while in transit between gateways.
!
crypto ipsec security-association replay window-size 128

! This option instructs the router to fragment the unencrypted packets
! (prior to encryption).
!
crypto ipsec fragmentation before-encryption
```

**Tunnel**

```
! #3: Tunnel Interface Configuration
!
! A tunnel interface is configured to be the logical interface associated
! with the tunnel. All traffic routed to the tunnel interface will be
! encrypted and transmitted to the VPC. Similarly, traffic from the VPC
! will be logically received on this interface.
!
! Association with the IPsec security association is done through the
! "tunnel protection" command.
!
! The address of the interface is configured with the setup for your
! Customer Gateway. If the address changes, the Customer Gateway and VPN
! Connection must be recreated with Amazon VPC.
!
interface Tunnel1
  ip address 169.254.255.2 255.255.255.252
  ip virtual-reassembly
  tunnel source YOUR_UPLINK_ADDRESS
  tunnel destination 72.21.209.225
  tunnel mode ipsec ipv4
  tunnel protection ipsec profile ipsec-vpn-44a8938f-0
  ! This option causes the router to reduce the Maximum Segment Size of
  ! TCP packets to prevent packet fragmentation.
  ip tcp adjust-mss 1396
  no shutdown
exit
```

**BGP**

```
! #4: Border Gateway Protocol (BGP) Configuration
!

! BGP is used within the tunnel to exchange prefixes between the
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
! Virtual Private Gateway and your Customer Gateway. The Virtual Private Gateway
! will announce the prefix corresponding to your VPC.
!
! Your Customer Gateway may announce a default route (0.0.0.0/0),
! which can be done with the 'network' statement and
! 'default-originate' statements.
!
! The BGP timers are adjusted to provide more rapid detection of outages.
!
! The local BGP Autonomous System Number (ASN) (YOUR_BGP_ASN) is configured
! as part of your Customer Gateway. If the ASN must be changed, the
! Customer Gateway and VPN Connection will need to be recreated with AWS.
!
router bgp YOUR_BGP_ASN
  neighbor 169.254.255.1 remote-as 7224
  neighbor 169.254.255.1 activate
  neighbor 169.254.255.1 timers 10 30 30
  address-family ipv4 unicast
    neighbor 169.254.255.1 remote-as 7224
    neighbor 169.254.255.1 timers 10 30 30
    neighbor 169.254.255.1 default-originate
    neighbor 169.254.255.1 activate
    neighbor 169.254.255.1 soft-reconfiguration inbound
! To advertise additional prefixes to Amazon VPC, copy the 'network' statement
! and identify the prefix you wish to advertise. Make sure the prefix is present
! in the routing table of the device with a valid next-hop.
  network 0.0.0.0
  exit
exit

! -----
! IPsec Tunnel #2
! -----

IKE

! #1: Internet Key Exchange (IKE) Configuration
!
! A policy is established for the supported ISAKMP encryption,
! authentication, Diffie-Hellman, lifetime, and key parameters.
!
! Note that there are a global list of ISAKMP policies, each identified by
! sequence number. This policy is defined as #201, which may conflict with
! an existing policy using the same number. If so, we recommend changing
! the sequence number to avoid conflicts.
!
crypto isakmp policy 201
  encryption aes 128
  authentication pre-share
  group 2
  lifetime 28800
  hash sha
exit

! The ISAKMP keyring stores the Pre Shared Key used to authenticate the
! tunnel endpoints.
!
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
crypto keyring keyring-vpn-44a8938f-1
  pre-shared-key address 72.21.209.193 key plain-text-password2
exit

! An ISAKMP profile is used to associate the keyring with the particular
! endpoint.
!
crypto isakmp profile isakmp-vpn-44a8938f-1
  match identity address 72.21.209.193
  keyring keyring-vpn-44a8938f-1
exit

IPsec

! #2: IPsec Configuration
!
! The IPsec transform set defines the encryption, authentication, and IPsec
! mode parameters.
!
crypto ipsec transform-set ipsec-prop-vpn-44a8938f-1 esp-aes 128 esp-sha-hmac

  mode tunnel
exit

! The IPsec profile references the IPsec transform set and further defines
! the Diffie-Hellman group and security association lifetime.
!
crypto ipsec profile ipsec-vpn-44a8938f-1
  set pfs group2
  set security-association lifetime seconds 3600
  set transform-set ipsec-prop-vpn-44a8938f-1
exit

! Additional parameters of the IPsec configuration are set here. Note that
! these parameters are global and therefore impact other IPsec
! associations.
! This option instructs the router to clear the "Don't Fragment"
! bit from packets that carry this bit and yet must be fragmented, enabling
! them to be fragmented.
!
crypto ipsec df-bit clear

! This option enables IPsec Dead Peer Detection, which causes periodic
! messages to be sent to ensure a Security Association remains operational.
!
crypto isakmp keepalive 10 10 on-demand

! This configures the gateway's window for accepting out of order
! IPsec packets. A larger window can be helpful if too many packets
! are dropped due to reordering while in transit between gateways.
!
crypto ipsec security-association replay window-size 128

! This option instructs the router to fragment the unencrypted packets
! (prior to encryption).
!
crypto ipsec fragmentation before-encryption
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

**Tunnel**

```
! #3: Tunnel Interface Configuration
!
! A tunnel interface is configured to be the logical interface associated
! with the tunnel. All traffic routed to the tunnel interface will be
! encrypted and transmitted to the VPC. Similarly, traffic from the VPC
! will be logically received on this interface.
!
! Association with the IPsec security association is done through the
! "tunnel protection" command.
!
! The address of the interface is configured with the setup for your
! Customer Gateway. If the address changes, the Customer Gateway and VPN
! Connection must be recreated with Amazon VPC.
!
interface Tunnel2
  ip address 169.254.255.6 255.255.255.252
  ip virtual-reassembly
  tunnel source YOUR_UPLINK_ADDRESS
  tunnel destination 72.21.209.193
  tunnel mode ipsec ipv4
  tunnel protection ipsec profile ipsec-vpn-44a8938f-1
  ! This option causes the router to reduce the Maximum Segment Size of
  ! TCP packets to prevent packet fragmentation.
  ip tcp adjust-mss 1396
  no shutdown
exit
```

**BGP**

```
! #4: Border Gateway Protocol (BGP) Configuration
!
! BGP is used within the tunnel to exchange prefixes between the
! Virtual Private Gateway and your Customer Gateway. The Virtual Private Gateway
! will announce the prefix corresponding to your Cloud.
!
! Your Customer Gateway may announce a default route (0.0.0.0/0),
! which can be done with the 'network' statement and
! 'default-originate' statements.
!
! The BGP timers are adjusted to provide more rapid detection of outages.
!
! The local BGP Autonomous System Number (ASN) (YOUR_BGP_ASN) is configured
! as part of your Customer Gateway. If the ASN must be changed, the
! Customer Gateway and VPN Connection will need to be recreated with AWS.
!
router bgp YOUR_BGP_ASN
  neighbor 169.254.255.5 remote-as 7224
  neighbor 169.254.255.5 activate
  neighbor 169.254.255.5 timers 10 30 30
  address-family ipv4 unicast
    neighbor 169.254.255.5 remote-as 7224
    neighbor 169.254.255.5 timers 10 30 30
    neighbor 169.254.255.5 default-originate
    neighbor 169.254.255.5 activate
```

```
neighbor 169.254.255.5 soft-reconfiguration inbound
! To advertise additional prefixes to Amazon VPC, copy the 'network' statement
! and identify the prefix you wish to advertise. Make sure the prefix is present
! in the routing table of the device with a valid next-hop.
network 0.0.0.0
exit
exit

! Additional Notes and Questions
! - Amazon Virtual Private Cloud Getting Started Guide:
!   http://docs.amazonwebservices.com/AWSVPC/latest/GettingStartedGuide
! - Amazon Virtual Private Cloud Network Administrator Guide:
!   http://docs.amazonwebservices.com/AWSVPC/latest/NetworkAdminGuide
```

## How to Test the Customer Gateway Configuration

You must first test the gateway configuration for each tunnel.

### To test the customer gateway configuration for each tunnel

1. On your customer gateway, determine if the BGP status is *Active*. It takes approximately 30 seconds for a BGP peering to become active.
2. Ensure that the customer gateway is advertising a route to the virtual private gateway. The route may be the default route (0.0.0.0/0) or a more specific route you prefer.

When properly established, your BGP peering should be receiving one route from the virtual private gateway corresponding to the prefix that your VPC integration team specified for the VPC (e.g., 10.0.0.0/24). If the BGP peering is established, you are receiving a prefix, and you are advertising a prefix, your tunnel is configured correctly. Make sure both tunnels are in this state.

Next you must test the connectivity for each tunnel.



### Important

For the connectivity test to work, you must configure any security group or network ACL in your VPC that filters traffic to the instance to allow inbound and outbound ICMP traffic.

### To test the end-to-end connectivity of each tunnel

1. Launch an instance of one of the Amazon Linux AMIs into your VPC. They're available in the Quick Start menu when you use the **Request Instances Wizard** in the AWS Management Console (for more information, see the [Amazon Virtual Private Cloud Getting Started Guide](#)).
2. After the instance is running, get its private IP address (e.g., 10.0.0.4). The console displays the address as part of the instance's details.
3. On a system in your home network, use the ping command with the instance's IP address. Make sure the computer you ping from is behind the customer gateway. A successful response should be similar to the following:

**Amazon Virtual Private Cloud Network Administrator  
Guide  
How to Test the Customer Gateway Configuration**

---

```
PROMPT> ping 10.0.0.4
Pinging 10.0.0.4 with 32 bytes of data:

Reply from 10.0.0.4: bytes=32 time<1ms TTL=128
Reply from 10.0.0.4: bytes=32 time<1ms TTL=128
Reply from 10.0.0.4: bytes=32 time<1ms TTL=128

Ping statistics for 10.0.0.4:
Packets: Sent = 3, Received = 3, Lost = 0 (0% loss),

Approximate round trip times in milliseconds:
Minimum = 0ms, Maximum = 0ms, Average = 0ms
```



**Note**

If you ping an instance from your customer gateway router, ensure you are sourcing ping messages from an internal IP address, not a tunnel IP address. Some AMLs will not respond to ping messages from the tunnel IP addresses.

If your tunnels do not test successfully, see [Troubleshooting \(p. 61\)](#).

# Example: Juniper JunOS Device

---

## Topics


- [A High-Level View of the Customer Gateway \(p. 24\)](#)
- [A Detailed View of the Customer Gateway and an Example Configuration \(p. 45\)](#)
- [How to Test the Customer Gateway Configuration \(p. 42\)](#)

This section shows an example of the configuration information your integration team gives you if your customer gateway is a Juniper J-Series router running JunOS 9.5 (or later) software.

Two diagrams accompany the example configuration: The first diagram shows the high-level layout of the customer gateway, the second diagram supplies details that match the example configuration. You should take the real configuration information that your integration team gives you and apply it to your customer gateway.

## A High-Level View of the Customer Gateway

The following diagram shows the general details of your customer gateway. The VPN connection consists of two separate tunnels: *st0.1* and *st0.2*. Two redundant tunnels provide an increased availability in the case of a device failure.



## A Detailed View of the Customer Gateway and an Example Configuration

The diagram in this section gives you a detailed illustration of an example Juniper JunOS customer gateway. After the diagram is a corresponding example of the configuration information your integration team should give you. The example configuration contains a set of information for each of the two tunnels you must configure.

In addition, the example configuration refers to these items that you must provide:

- **YOUR\_UPLINK\_ADDRESS**—The IP address for the Internet-routable external interface on the customer gateway (which must be static and can't be behind a device performing NAT)
- **YOUR\_BGP\_ASN**—The customer gateway's BGP ASN (we use 65000 by default)


The example configuration includes several dummy values to help you understand how configuration works. For example, we give dummy values for the VPN connection ID (44a8938f), Virtual Private Gateway ID (8db04f81), the IP addresses (e.g., 72.21.209.\*, 169.254.255.\*), and the remote ASN (7224). The actual configuration information you get will replace the dummy values to real values.

In addition to the configuration changes, you must:

- Configure the outside interface (referred to as ge-0/0/0.0 in the example configuration)
- Configure the tunnel interface IDs (referred to as st0.1 and st0.2 in the example configuration)
- Configure all internal routing (getting traffic between the customer gateway and your local network)
- Identify the security zone for the uplink interface (the following configuration information uses the default "untrust" zone)
- Identify the security zone for the inside interface (the following configuration information uses the default "trust" zone)

In the following diagram and example configuration the items highlighted in red *italic* need to be replaced with values that apply to your own particular situation.

**Amazon Virtual Private Cloud Network Administrator  
Guide**  
**A Detailed View of the Customer Gateway and an  
Example Configuration**



**Important**

The following configuration information is an example of what the Amazon VPC API provides you. Many of the values in the following example will be different from the actual configuration information that you receive from the API. You must use the values from the API and not the example values shown here or your implementation will fail.

```
# Amazon Web Services
# Virtual Private Cloud
#
# AWS utilizes unique identifiers to manipulate the configuration of
# a VPN Connection. Each VPN Connection is assigned a VPN Connection
# Identifier and is associated with two other identifiers, namely the
# Customer Gateway Identifier and the Virtual Private Gateway Identifier.
#
# Your VPN Connection ID           : vpn-44a8938f
# Your Virtual Private Gateway ID  : vgw-8db04f81
# Your Customer Gateway ID        : cgw-b4dc3961
#
# This configuration consists of two tunnels. Both tunnels must be
# configured on your Customer Gateway.
#
# -----
# IPsec Tunnel #1
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
# -----  
IKE  
# #1: Internet Key Exchange (IKE) Configuration  
#  
# A proposal is established for the supported IKE encryption,  
# authentication, Diffie-Hellman, and lifetime parameters.  
#  
set security ike proposal ike-prop-vpn-44a8938f-1 authentication-method pre-  
shared-keys  
set security ike proposal ike-prop-vpn-44a8938f-1 authentication-algorithm sha1  
set security ike proposal ike-prop-vpn-44a8938f-1 encryption-algorithm aes-128-  
cbc  
set security ike proposal ike-prop-vpn-44a8938f-1 lifetime-seconds 28800  
set security ike proposal ike-prop-vpn-44a8938f-1 dh-group group2  
  
# An IKE policy is established to associate a Pre Shared Key with the  
# defined proposal.  
#  
set security ike policy ike-pol-vpn-44a8938f-1 mode main  
set security ike policy ike-pol-vpn-44a8938f-1 proposals ike-prop-vpn-44a8938f-  
0  
set security ike policy ike-pol-vpn-44a8938f-1 pre-shared-key ascii-text plain-  
text-password1  
  
# The IKE gateway is defined to be the Virtual Private Gateway. The gateway  
# configuration associates a local interface, remote IP address, and  
# IKE policy.  
#  
# This example shows the outside of the tunnel as interface ge-0/0/0.0.  
# This should be set to the interface that IP address YOUR_UPLINK_ADDRESS is  
# associated with.  
# This address is configured with the setup for your Customer Gateway.  
#  
# If the address changes, the Customer Gateway and VPN Connection must  
# be recreated.  
set security ike gateway gw-vpn-44a8938f-1 ike-policy ike-pol-vpn-44a8938f-0  
set security ike gateway gw-vpn-44a8938f-1 external-interface ge-0/0/0.0  
set security ike gateway gw-vpn-44a8938f-1 address 72.21.209.225  
  
# Troubleshooting IKE connectivity can be aided by enabling IKE tracing.  
# The configuration below will cause the router to log IKE messages to  
# the 'kmd' log. Run 'show messages kmd' to retrieve these logs.  
# set security ike traceoptions file kmd  
# set security ike traceoptions file size 1024768  
# set security ike traceoptions file files 10  
# set security ike traceoptions flag all  
  
IPsec  
# #2: IPsec Configuration  
#  
# The IPsec proposal defines the protocol, authentication, encryption, and  
# lifetime parameters for our IPsec security association.  
#  
set security ipsec proposal ipsec-prop-vpn-44a8938f-1 protocol esp  
set security ipsec proposal ipsec-prop-vpn-44a8938f-1 authentication-algorithm  
hmac-sha1-96
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
set security ipsec proposal ipsec-prop-vpn-44a8938f-1 encryption-algorithm aes-128-cbc
set security ipsec proposal ipsec-prop-vpn-44a8938f-1 lifetime-seconds 3600

# The IPsec policy incorporates the Diffie-Hellman group and the IPsec
# proposal.
#
set security ipsec policy ipsec-pol-vpn-44a8938f-1 perfect-forward-secrecy keys
group2
set security ipsec policy ipsec-pol-vpn-44a8938f-1 proposals ipsec-prop-vpn-44a8938f-0

# A security association is defined here. The IPsec Policy and IKE gateways
# are associated with a tunnel interface (st0.1).
# The tunnel interface ID is assumed; if other tunnels are defined on
# your router, you will need to specify a unique interface name
# (for example, st0.10).
#
set security ipsec vpn vpn-44a8938f-1 bind-interface st0.1
set security ipsec vpn vpn-44a8938f-1 ike gateway gw-vpn-44a8938f-0
set security ipsec vpn vpn-44a8938f-1 ike ipsec-policy ipsec-pol-vpn-44a8938f-0
set security ipsec vpn vpn-44a8938f-1 df-bit clear

# This option enables IPsec Dead Peer Detection, which causes periodic
# messages to be sent to ensure a Security Association remains operational.
#
set security ike gateway gw-vpn-44a8938f-1 dead-peer-detection
```

**Tunnel**

```
# #3: Tunnel Interface Configuration
#
# The tunnel interface is configured with the internal IP address.
#
set interfaces st0.1 family inet address 169.254.255.2/30
set interfaces st0.1 family inet mtu 1436
set security zones security-zone trust interfaces st0.1

# The security zone protecting external interfaces of the router must be
# configured to allow IKE traffic inbound.
#
set security zones security-zone untrust host-inbound-traffic system-services
ike

# The security zone protecting internal interfaces (including the logical
# tunnel interfaces) must be configured to allow BGP traffic inbound.
#
set security zones security-zone trust host-inbound-traffic protocols bgp

# This option causes the router to reduce the Maximum Segment Size of
# TCP packets to prevent packet fragmentation.
#
set security flow tcp-mss ipsec-vpn mss 1396
```

**BGP**

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
# #4: Border Gateway Protocol (BGP) Configuration
#
# BGP is used within the tunnel to exchange prefixes between the
# Virtual Private Gateway and your Customer Gateway. The Virtual Private Gateway
#
# will announce the prefix corresponding to your VPC.
#
# Your Customer Gateway may announce a default route (0.0.0.0/0),
# which can be done with the EXPORT-DEFAULT policy. Only one prefix is
# accepted by the Virtual Private Gateway.
#
# The BGP timers are adjusted to provide more rapid detection of outages.
#
# The local BGP Autonomous System Number (ASN) (YOUR_BGP_ASN) is configured
# as part of your Customer Gateway. If the ASN must be changed, the
# Customer Gateway and VPN Connection will need to be recreated with AWS.
#
# We establish a basic route policy to export a default route to the
# Virtual Private Gateway.
#
set policy-options policy-statement EXPORT-DEFAULT term default from route-
filter 0.0.0.0/0 exact

set policy-options policy-statement EXPORT-DEFAULT term default then accept

set policy-options policy-statement EXPORT-DEFAULT term reject then reject

set protocols bgp group ebgp type external

set protocols bgp group ebgp neighbor 169.254.255.1 export EXPORT-DEFAULT
set protocols bgp group ebgp neighbor 169.254.255.1 peer-as 7224
set protocols bgp group ebgp neighbor 169.254.255.1 hold-time 30
set protocols bgp group ebgp neighbor 169.254.255.1 local-as YOUR_BGP_ASN

# -----
# IPsec Tunnel #2
# -----

IKE

# #1: Internet Key Exchange (IKE) Configuration
#
# A proposal is established for the supported IKE encryption,
# authentication, Diffie-Hellman, and lifetime parameters.
#
set security ike proposal ike-prop-vpn-44a8938f-2 authentication-method pre-
shared-keys
set security ike proposal ike-prop-vpn-44a8938f-2 authentication-algorithm sha1
set security ike proposal ike-prop-vpn-44a8938f-2 encryption-algorithm aes-128-
cbc
set security ike proposal ike-prop-vpn-44a8938f-2 lifetime-seconds 28800
set security ike proposal ike-prop-vpn-44a8938f-2 dh-group group2

# An IKE policy is established to associate a Pre Shared Key with the
# defined proposal.
#
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
set security ike policy ike-pol-vpn-44a8938f-2 mode main
set security ike policy ike-pol-vpn-44a8938f-2 proposals ike-prop-vpn-44a8938f-2
set security ike policy ike-pol-vpn-44a8938f-2 pre-shared-key ascii-text plain-text-password2

# The IKE gateway is defined to be the Virtual Private Gateway. The gateway
# configuration associates a local interface, remote IP address, and
# IKE policy.
#
# This example shows the outside of the tunnel as interface ge-0/0/0.0.
# This should be set to the interface that IP address YOUR_UPLINK_ADDRESS is
# associated with.
# This address is configured with the setup for your Customer Gateway.
#
# If the address changes, the Customer Gateway and VPN Connection must be recreated.
#
set security ike gateway gw-vpn-44a8938f-2 ike-policy ike-pol-vpn-44a8938f-1
set security ike gateway gw-vpn-44a8938f-2 external-interface ge-0/0/0.0
set security ike gateway gw-vpn-44a8938f-2 address 72.21.209.193

# Troubleshooting IKE connectivity can be aided by enabling IKE tracing.
# The configuration below will cause the router to log IKE messages to
# the 'kmd' log. Run 'show messages kmd' to retrieve these logs.
# set security ike traceoptions file kmd
# set security ike traceoptions file size 1024768
# set security ike traceoptions file files 10
# set security ike traceoptions flag all
```

**IPsec**

```
# #2: IPsec Configuration
#
# The IPsec proposal defines the protocol, authentication, encryption, and
# lifetime parameters for our IPsec security association.
#
set security ipsec proposal ipsec-prop-vpn-44a8938f-2 protocol esp
set security ipsec proposal ipsec-prop-vpn-44a8938f-2 authentication-algorithm
  hmac-shal-96
set security ipsec proposal ipsec-prop-vpn-44a8938f-2 encryption-algorithm aes-128-cbc
set security ipsec proposal ipsec-prop-vpn-44a8938f-2 lifetime-seconds 3600

# The IPsec policy incorporates the Diffie-Hellman group and the IPsec
# proposal.
#
set security ipsec policy ipsec-pol-vpn-44a8938f-2 perfect-forward-secrecy keys
  group2
set security ipsec policy ipsec-pol-vpn-44a8938f-2 proposals ipsec-prop-vpn-44a8938f-2

# A security association is defined here. The IPsec Policy and IKE gateways
# are associated with a tunnel interface (st0.2).
# The tunnel interface ID is assumed; if other tunnels are defined on
# your router, you will need to specify a unique interface name
# (for example, st0.20).
#
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
set security ipsec vpn vpn-44a8938f-2 bind-interface st0.2
set security ipsec vpn vpn-44a8938f-2 ike gateway gw-vpn-44a8938f-2
set security ipsec vpn vpn-44a8938f-2 ike ipsec-policy ipsec-pol-vpn-44a8938f-2
set security ipsec vpn vpn-44a8938f-2 df-bit clear

# This option enables IPsec Dead Peer Detection, which causes periodic
# messages to be sent to ensure a Security Association remains operational.
#
set security ike gateway gw-vpn-44a8938f-2 dead-peer-detection
```

**Tunnel**

```
# #3: Tunnel Interface Configuration
#

# The tunnel interface is configured with the internal IP address.
#
set interfaces st0.2 family inet address 169.254.255.6/30
set interfaces st0.2 family inet mtu 1436
set security zones security-zone trust interfaces st0.2

# The security zone protecting external interfaces of the router must be
# configured to allow IKE traffic inbound.
#
set security zones security-zone untrust host-inbound-traffic system-services
ike

# The security zone protecting internal interfaces (including the logical
# tunnel interfaces) must be configured to allow BGP traffic inbound.
#
set security zones security-zone trust host-inbound-traffic protocols bgp

# This option causes the router to reduce the Maximum Segment Size of
# TCP packets to prevent packet fragmentation.
#
set security flow tcp-mss ipsec-vpn mss 1396
```

**BGP**

```
# #4: Border Gateway Protocol (BGP) Configuration
#

# BGP is used within the tunnel to exchange prefixes between the
# Virtual Private Gateway and your Customer Gateway. The Virtual Private Gateway
# will announce the prefix corresponding to your VPC.
#
# Your Customer Gateway may announce a default route (0.0.0.0/0),
# which can be done with the EXPORT-DEFAULT policy. Only one prefix is
# accepted by the Virtual Private Gateway.
#

# The BGP timers are adjusted to provide more rapid detection of outages.
#

# The local BGP Autonomous System Number (ASN) (YOUR_BGP_ASN) is configured
# as part of your Customer Gateway. If the ASN must be changed, the
```

```
# Customer Gateway and VPN Connection will need to be recreated with AWS.
#
# We establish a basic route policy to export a default route to the
# Virtual Private Gateway.
#
set policy-options policy-statement EXPORT-DEFAULT term default from route-
filter 0.0.0.0/0 exact

set policy-options policy-statement EXPORT-DEFAULT term default then accept

set policy-options policy-statement EXPORT-DEFAULT term reject then reject

set protocols bgp group ebgp type external

set protocols bgp group ebgp neighbor 169.254.255.5 export EXPORT-DEFAULT
set protocols bgp group ebgp neighbor 169.254.255.5 peer-as 7224
set protocols bgp group ebgp neighbor 169.254.255.5 hold-time 30
set protocols bgp group ebgp neighbor 169.254.255.5 local-as YOUR_BGP_ASN

# -----
# Additional Notes and Questions
# - Amazon Virtual Private Cloud Getting Started Guide:
#   http://docs.amazonwebservices.com/AWSVPC/latest/GettingStartedGuide
# - Amazon Virtual Private Cloud Network Administrator Guide:
#   http://docs.amazonwebservices.com/AWSVPC/latest/NetworkAdminGuide
```

## How to Test the Customer Gateway Configuration

You must first test the gateway configuration for each tunnel.

### To test the customer gateway configuration for each tunnel

1. On your customer gateway, determine if the BGP status is *Active*. It takes approximately 30 seconds for a BGP peering to become active.
2. Ensure that the customer gateway is advertising a route to the virtual private gateway. The route may be the default route (0.0.0.0/0) or a more specific route you prefer.

When properly established, your BGP peering should be receiving one route from the virtual private gateway corresponding to the prefix that your VPC integration team specified for the VPC (e.g., 10.0.0.0/24). If the BGP peering is established, you are receiving a prefix, and you are advertising a prefix, your tunnel is configured correctly. Make sure both tunnels are in this state.

Next you must test the connectivity for each tunnel.



### Important

For the connectivity test to work, you must configure any security group or network ACL in your VPC that filters traffic to the instance to allow inbound and outbound ICMP traffic.

### To test the end-to-end connectivity of each tunnel

1. Launch an instance of one of the Amazon Linux AMIs into your VPC. They're available in the Quick Start menu when you use the **Request Instances Wizard** in the AWS Management Console (for more information, see the [Amazon Virtual Private Cloud Getting Started Guide](#)).
2. After the instance is running, get its private IP address (e.g., 10.0.0.4). The console displays the address as part of the instance's details.
3. On a system in your home network, use the ping command with the instance's IP address. Make sure the computer you ping from is behind the customer gateway. A successful response should be similar to the following:

```
PROMPT> ping 10.0.0.4
Pinging 10.0.0.4 with 32 bytes of data:

Reply from 10.0.0.4: bytes=32 time<1ms TTL=128
Reply from 10.0.0.4: bytes=32 time<1ms TTL=128
Reply from 10.0.0.4: bytes=32 time<1ms TTL=128

Ping statistics for 10.0.0.4:
    Packets: Sent = 3, Received = 3, Lost = 0 (0% loss),

Approximate round trip times in milliseconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
```



#### Note

If you ping an instance from your customer gateway router, ensure you are sourcing ping messages from an internal IP address, not a tunnel IP address. Some AMIs will not respond to ping messages from the tunnel IP addresses.

If your tunnels do not test successfully, see [Troubleshooting \(p. 61\)](#).

# Example: Juniper ScreenOS Device

---

## Topics


- [A High-Level View of the Customer Gateway \(p. 35\)](#)
- [A Detailed View of the Customer Gateway and an Example Configuration \(p. 45\)](#)
- [How to Test the Customer Gateway Configuration \(p. 42\)](#)

This section shows an example of the configuration information your integration team gives you if your customer gateway is a Juniper SSG or Netscreen series device running Juniper ScreenOS software.

Two diagrams accompany the example configuration: The first diagram shows the high-level layout of the customer gateway, the second diagram supplies details that match the example configuration. You should take the real configuration information that your integration team gives you and apply it to your customer gateway.

## A High-Level View of the Customer Gateway

The following diagram shows the general details of your customer gateway. The VPN connection consists of two separate tunnels: *tunnel.1* and *tunnel.2*. Two redundant tunnels provide an increased availability in the case of a device failure.



## A Detailed View of the Customer Gateway and an Example Configuration

The diagram in this section shows an example Juniper ScreenOS customer gateway. After the diagram is a corresponding example of the configuration information your integration team should give you. The example configuration contains information for each of the two tunnels you must configure.

In addition, the example configuration refers to these items that you must provide:

- **YOUR\_UPLINK\_ADDRESS**—The IP address for the Internet-routable external interface on the customer gateway (the address must be static and can't be behind a device performing NAT)
- **YOUR\_BGP\_ASN**—The customer gateway's BGP ASN (we use 65000 by default)


The example configuration includes several dummy values to help you understand how configuration works. For example, we give dummy values for the VPN connection ID (44a8938f), virtual private gateway ID (8db04f81), the IP addresses (e.g., 72.21.209.\*, 169.254.255.\*), and the remote ASN (7224). The actual configuration information you get will replace the dummy values with real values.

You must also configure:

- The outside interface (referred to as ethernet0/0 in the example configuration)
- The tunnel interface IDs (referred to as tunnel.1 and tunnel.2 in the example configuration)
- All internal routing (getting traffic between the customer gateway and your local network)

In the following diagram and example configuration the items highlighted in red italic need to be replaced with values that apply to your own particular situation.

**Amazon Virtual Private Cloud Network Administrator  
Guide**  
**A Detailed View of the Customer Gateway and an  
Example Configuration**



**Important**

The following configuration information is an example of what your integration team provides you. Many of the values in the following example will be different from the configuration information that you actually receive. Of course, you must use the actual values and not the example values shown here or your implementation will fail.



**Important**

The configuration below is appropriate for ScreenOS versions 6.2 and newer. A separate configuration is available for ScreenOS version 6.1.

```
# Amazon Web Services
# Virtual Private Cloud
#
# AWS utilizes unique identifiers to manipulate the configuration of a VPN
# Connection. Each VPN Connection is assigned a VPN Connection Identifier
# and is associated with two other identifiers, namely the Customer Gateway
# Identifier and the Virtual Private Gateway Identifier.
#
# Your VPN Connection ID           : vpn-44a8938f
# Your Virtual Private Gateway ID  : vgw-8db04f81
# Your Customer Gateway ID        : cgw-b4dc3961
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
#
# This configuration consists of two tunnels. Both tunnels must be configured
# on your Customer Gateway.
#
# This configuration was tested on a Juniper SSG-5 running ScreenOS 6.3R2.
#
# -----
----
# IPsec Tunnel #1
# -----
----

IKE

# #1: Internet Key Exchange (IKE) Configuration
#
# A proposal is established for the supported IKE encryption, authentication,
# Diffie-Hellman, and lifetime parameters.
#

set ike p1-proposal ike-prop-vpn-44a8938f-1 preshare group2 esp aes128 sha-1
second 28800

# The IKE gateway is defined to be the Virtual Private Gateway. The gateway
# configuration
# associates a local interface, remote IP address, and IKE policy.
#
# This example shows the outside of the tunnel as interface ethernet0/0. This
# should be set to the interface that IP address YOUR_UPLINK_ADDRESS is
# associated with.
#
# This address is configured with the setup for your Customer Gateway. If the
# address changes, the Customer Gateway and VPN Connection must be recreated.
#

set ike gateway gw-vpn-44a8938f-1 address 72.21.209.225 id 72.21.209.225 main
outgoing-interface ethernet0/0 preshare "plain-text-password1" proposal ike-
prop-vpn-44a8938f-1

# Troubleshooting IKE connectivity can be aided by enabling IKE debugging.
# To do so, run the following commands:
# clear dbuf          -- Clear debug buffer
# debug ike all      -- Enable IKE debugging
# get dbuf stream    -- View debug messages
# undebuf all        -- Turn off debugging

IPsec

# #2: IPsec Configuration
#
# The IPsec (Phase 2) proposal defines the protocol, authentication,
# encryption, and lifetime parameters for our IPsec security association.
#

set ike p2-proposal ipsec-prop-vpn-44a8938f-1 group2 esp aes128 sha-1 second
3600
set ike gateway gw-vpn-44a8938f-1 dpd-liveness interval 10
set vpn IPSEC-vpn-44a8938f-1 gateway gw-vpn-44a8938f-1 replay tunnel proposal
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

ipsec-prop-vpn-44a8938f-1

**Tunnel**

```
# #3: Tunnel Interface Configuration
#
# The tunnel interface is configured with the internal IP address.
#
# To establish connectivity between your internal network and the VPC, you
# must have an interface facing your internal network in the "Trust" zone.
#

set interface tunnel.1 zone Trust
set interface tunnel.1 ip 169.254.255.2/30
set interface tunnel.1 mtu 1436
set vpn IPSEC-vpn-44a8938f-1 bind interface tunnel.1

# By default, the router will block asymmetric VPN traffic, which may occur
# with this VPN Connection. This occurs, for example, when routing policies
# cause traffic to sent from your router to VPC through one IPsec tunnel
# while traffic returns from VPC through the other.
#
# This command allows this traffic to be received by your device.

set zone Trust asymmetric-vpn

# This option causes the router to reduce the Maximum Segment Size of TCP
# packets to prevent packet fragmentation.
#

set flow vpn-tcp-mss 1396
```

**BGP**

```
# #4: Border Gateway Protocol (BGP) Configuration
#
# BGP is used within the tunnel to exchange prefixes between the Virtual Private
# Gateway
# and your Customer Gateway. The Virtual Private Gateway will announce the
# prefix
# corresponding to your VPC.
#
# Your Customer Gateway may announce a default route (0.0.0.0/0).
#
# The BGP timers are adjusted to provide more rapid detection of outages.
#
# The local BGP Autonomous System Number (ASN) (YOUR_BGP_ASN) is configured
# as part of your Customer Gateway. If the ASN must be changed, the
# Customer Gateway and VPN Connection will need to be recreated with AWS.
#

set vrouter trust-vr
set max-ecmp-routes 2
set protocol bgp YOUR_BGP_ASN
set hold-time 30
set ipv4 network 0.0.0.0/0
# To advertise additional prefixes to Amazon VPC, copy the 'network' statement
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
and
# identify the prefix you wish to advertise (set network X.X.X.X/X). Make sure
the
# prefix is present in the routing table of the device with a valid next-hop.
set ipv4 advertise-def-route
set enable
set neighbor 169.254.255.1 remote-as 7224
set neighbor 169.254.255.1 enable
set ipv4 neighbor 169.254.255.1 activate
exit
exit
set interface tunnel.1 protocol bgp
```

```
# -----
# IPsec Tunnel #2
# -----
```

#### **IKE**

```
# #1: Internet Key Exchange (IKE) Configuration
#
# A proposal is established for the supported IKE encryption, authentication,
# Diffie-Hellman, and lifetime parameters.
#
```

```
set ike p1-proposal ike-prop-vpn-44a8938f-2 preshare group2 esp aes128 sha-1
second 28800
```

```
# The IKE gateway is defined to be the Virtual Private Gateway. The gateway
configuration
# associates a local interface, remote IP address, and IKE policy.
#
# This example shows the outside of the tunnel as interface ethernet0/0. This
# should be set to the interface that IP address YOUR_UPLINK_ADDRESS is
# associated with.
```

```
# This address is configured with the setup for your Customer Gateway. If the
# address changes, the Customer Gateway and VPN Connection must be recreated.
#
set ike gateway gw-vpn-44a8938f-2 address 72.21.209.193 id 72.21.209.193 main
outgoing-interface ethernet0/0 preshare "plain-text-password2" proposal ike-
prop-vpn-44a8938f-2
```

```
# Troubleshooting IKE connectivity can be aided by enabling IKE debugging.
# To do so, run the following commands:
# clear dbuf          -- Clear debug buffer
# debug ike all      -- Enable IKE debugging
# get dbuf stream    -- View debug messages
# undebuf all        -- Turn off debugging
```

#### **IPsec**

```
# #2: IPsec Configuration
#
# The IPsec (Phase 2) proposal defines the protocol, authentication,
# encryption, and lifetime parameters for our IPsec security association.
#
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
set ike p2-proposal ipsec-prop-vpn-44a8938f-2 group2 esp aes128 sha-1 second
3600
set ike gateway gw-vpn-44a8938f-2 dpd-liveness interval 10
set vpn IPSEC-vpn-44a8938f-2 gateway gw-vpn-44a8938f-2 replay tunnel proposal
ipsec-prop-vpn-44a8938f-2
```

**Tunnel**

```
# #3: Tunnel Interface Configuration
#
# The tunnel interface is configured with the internal IP address.
#
# To establish connectivity between your internal network and the VPC, you
# must have an interface facing your internal network in the "Trust" zone.
```

```
set interface tunnel.2 zone Trust
set interface tunnel.2 ip 169.254.255.6/30
set interface tunnel.2 mtu 1436
set vpn IPSEC-vpn-44a8938f-2 bind interface tunnel.2
```

```
# By default, the router will block asymmetric VPN traffic, which may occur
# with this VPN Connection. This occurs, for example, when routing policies
# cause traffic to sent from your router to VPC through one IPsec tunnel
# while traffic returns from VPC through the other.
```

```
#
# This command allows this traffic to be received by your device.
```

```
set zone Trust asymmetric-vpn
```

```
# This option causes the router to reduce the Maximum Segment Size of TCP
# packets to prevent packet fragmentation.
```

```
set flow vpn-tcp-mss 1396
```

**BGP**

```
# #4: Border Gateway Protocol (BGP) Configuration
#
# BGP is used within the tunnel to exchange prefixes between the Virtual Private
# Gateway
# and your Customer Gateway. The Virtual Private Gateway will announce the
# prefix
# corresponding to your VPC.
```

```
#
# Your Customer Gateway may announce a default route (0.0.0.0/0).
```

```
#
# The BGP timers are adjusted to provide more rapid detection of outages.
```

```
#
# The local BGP Autonomous System Number (ASN) (YOUR_BGP_ASN) is configured
# as part of your Customer Gateway. If the ASN must be changed, the
# Customer Gateway and VPN Connection will need to be recreated with AWS.
```

```
#
set vrouter trust-vr
set max-ecmp-routes 2
set protocol bgp YOUR_BGP_ASN
set hold-time 30
set ipv4 network 0.0.0.0/0
```

```
# To advertise additional prefixes to Amazon VPC, copy the 'network' statement
and
# identify the prefix you wish to advertise (set network X.X.X.X/X). Make sure
the
# prefix is present in the routing table of the device with a valid next-hop.
set ipv4 advertise-def-route
set enable
set neighbor 169.254.255.5 remote-as 7224
set neighbor 169.254.255.5 enable
set ipv4 neighbor 169.254.255.5 activate
exit
exit
set interface tunnel.2 protocol bgp

# Additional Notes and Questions
# - Amazon Virtual Private Cloud Getting Started Guide:
#   http://docs.amazonwebservices.com/AWSVPC/latest/GettingStartedGuide
# - Amazon Virtual Private Cloud Network Administrator Guide:
#   http://docs.amazonwebservices.com/AWSVPC/latest/NetworkAdminGuide
```

## How to Test the Customer Gateway Configuration

You must first test the gateway configuration for each tunnel.

### To test the customer gateway configuration for each tunnel

1. On your customer gateway, determine if the BGP status is *Active*. It takes approximately 30 seconds for a BGP peering to become active.
2. Ensure that the customer gateway is advertising a route to the virtual private gateway. The route may be the default route (0.0.0.0/0) or a more specific route you prefer.

When properly established, your BGP peering should be receiving one route from the virtual private gateway corresponding to the prefix that your VPC integration team specified for the VPC (e.g., 10.0.0.0/24). If the BGP peering is established, you are receiving a prefix, and you are advertising a prefix, your tunnel is configured correctly. Make sure both tunnels are in this state.

Next you must test the connectivity for each tunnel.



### Important

For the connectivity test to work, you must configure any security group or network ACL in your VPC that filters traffic to the instance to allow inbound and outbound ICMP traffic.

### To test the end-to-end connectivity of each tunnel

1. Launch an instance of one of the Amazon Linux AMIs into your VPC. They're available in the Quick Start menu when you use the **Request Instances Wizard** in the AWS Management Console (for more information, see the [Amazon Virtual Private Cloud Getting Started Guide](#)).
2. After the instance is running, get its private IP address (e.g., 10.0.0.4). The console displays the address as part of the instance's details.

**Amazon Virtual Private Cloud Network Administrator  
Guide  
How to Test the Customer Gateway Configuration**

---

3. On a system in your home network, use the ping command with the instance's IP address. Make sure the computer you ping from is behind the customer gateway. A successful response should be similar to the following:

```
PROMPT> ping 10.0.0.4
Pinging 10.0.0.4 with 32 bytes of data:

Reply from 10.0.0.4: bytes=32 time<1ms TTL=128
Reply from 10.0.0.4: bytes=32 time<1ms TTL=128
Reply from 10.0.0.4: bytes=32 time<1ms TTL=128

Ping statistics for 10.0.0.4:
    Packets: Sent = 3, Received = 3, Lost = 0 (0% loss),

Approximate round trip times in milliseconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
```



**Note**

If you ping an instance from your customer gateway router, ensure you are sourcing ping messages from an internal IP address, not a tunnel IP address. Some AMLs will not respond to ping messages from the tunnel IP addresses.

If your tunnels do not test successfully, see [Troubleshooting \(p. 61\)](#).

# Example: Yamaha Device

---

## Topics


- [A High-Level View of the Customer Gateway \(p. 45\)](#)
- [A Detailed View of the Customer Gateway and an Example Configuration \(p. 45\)](#)
- [How to Test the Customer Gateway Configuration \(p. 59\)](#)

This section shows an example of the configuration information your integration team gives you if your customer gateway is a Yamaha RT107e, RTX1200, RTX1500, RTX3000 or SRT100 router.

Two diagrams accompany the example configuration: The first diagram shows the high-level layout of the customer gateway, the second diagram supplies details that match the example configuration. You should take the real configuration information that your integration team gives you and apply it to your customer gateway.

## A High-Level View of the Customer Gateway

The following diagram shows the general details of your customer gateway. The VPN connection consists of two separate tunnels: *Tunnel 1* and *Tunnel 2*. Two redundant tunnels provide an increased availability in the case of a device failure.



## A Detailed View of the Customer Gateway and an Example Configuration

The diagram in this section gives you a detailed illustration of an example Yamaha customer gateway. After the diagram is a corresponding example of the configuration information your integration team should give you. The example configuration contains a set of information for each of the two tunnels you must configure.

In addition, the example configuration refers to these items that you must provide:

- **YOUR\_UPLINK\_ADDRESS**—The IP address for the Internet-routable external interface on the customer gateway (which must be static and can't be behind a device performing NAT)

## Amazon Virtual Private Cloud Network Administrator Guide

### A Detailed View of the Customer Gateway and an Example Configuration


- **YOUR\_LOCAL\_NETWORK\_ADDRESS**—The IP address that is assigned to the LAN interface which is connected to your local network (most likely a private address such as 192.168.0.1)
- **YOUR\_BGP\_ASN**—The customer gateway's BGP ASN (we use 65000 by default)

The example configuration includes several dummy values to help you understand how configuration works. For example, we give dummy values for the VPN connection ID (44a8938f), Virtual Private Gateway ID (8db04f81), the IP addresses (e.g., 72.21.209.\*, 169.254.255.\*), and the remote ASN (7224). The actual configuration information you get will replace the dummy values with real values.

You must also configure:

- The outside interface (referred to as LAN3 in the example configuration)
- The tunnel interface IDs (referred to as tunnel 1 and tunnel 2 in the example configuration)
- All internal routing (getting traffic between the customer gateway and your local network)

In the following diagram and example configuration the items highlighted in red italic need to be replaced with values that apply to your own particular situation.



#### Important

The following configuration information is an example of what the Amazon VPC API provides you. Many of the values in the following example will be different from the actual configuration information that you receive from the API. You must use the values from the API and not the example values shown here or your implementation will fail.

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
# Amazon Web Services
# Virtual Private Cloud

# AWS utilizes unique identifiers to manage the configuration of
# a VPN Connection. Each VPN Connection is assigned an identifier and is
# associated with two other identifiers, namely the
# Customer Gateway Identifier and Virtual Private Gateway Identifier.
#
# Your VPN Connection ID           : vpn-44a8938f
# Your Virtual Private Gateway ID   : vgw-8db04f81
# Your Customer Gateway ID         : cgw-b4dc3961
#
#
```

```
# This configuration consists of two tunnels. Both tunnels must be
# configured on your Customer Gateway.
#
```

```
# -----
----
# IPsec Tunnel #1
# -----
----
```

**IKE**

```
# #1: Internet Key Exchange (IKE) Configuration
#
# A policy is established for the supported ISAKMP encryption,
# authentication, Diffie-Hellman, lifetime, and key parameters.
#
tunnel select 1
ipsec ike encryption 1 aes-cbc
ipsec ike group 1 modp1024
ipsec ike hash 1 sha

# The ISAKMP keyring stores the Pre Shared Key used to authenticate the
# tunnel endpoints.
#
ipsec ike pre-shared-key 1 text plain-text-password1
```

**IPsec**

```
# #2: IPsec Configuration

# The IPsec policy defines the encryption, authentication, and IPsec
# mode parameters.

# Note that there is a global list of IPsec policies, each identified by
# sequence number. This policy is defined as #200, which may conflict with
# an existing policy using the same number. If so, we recommend changing
# the sequence number to avoid conflicts.
#

ipsec tunnel 200
ipsec sa policy 200 1 esp aes-cbc sha-hmac

# The IPsec profile references the IPsec policy and further defines
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
# the Diffie-Hellman group and security association lifetime.

ipsec ike duration ipsec-sa 1 3600
ipsec ike pfs 1 on

# Additional parameters of the IPsec configuration are set here. Note that
# these parameters are global and therefore impact other IPsec
# associations.
# This option instructs the router to clear the "Don't Fragment"
# bit from packets that carry this bit and yet must be fragmented, enabling
# them to be fragmented.
#
ipsec tunnel outer df-bit clear

# This option enables IPsec Dead Peer Detection, which causes periodic
# messages to be sent to ensure a Security Association remains operational.

ipsec ike keepalive use 1 on dpd 10 3
```

**Tunnel**

```
# -----
----
# #3: Tunnel Interface Configuration
#
# A tunnel interface is configured to be the logical interface associated
# with the tunnel. All traffic routed to the tunnel interface will be
# encrypted and transmitted to the VPC. Similarly, traffic from the VPC
# will be logically received on this interface.
#
#
# The address of the interface is configured with the setup for your
# Customer Gateway. If the address changes, the Customer Gateway and VPN
# Connection must be recreated with Amazon VPC.
#
ipsec ike local address 1 YOUR_LOCAL_NETWORK_ADDRESS
ipsec ike remote address 1 72.21.209.225
ip tunnel address 169.254.255.2/30
ip tunnel remote address 169.254.255.1

# This option causes the router to reduce the Maximum Segment Size of
# TCP packets to prevent packet fragmentation

ip tunnel tcp mss limit 1396
tunnel enable 1
no tunnel select 1
ipsec auto refresh on
```

**BGP**

```
# -----
----
# #4: Border Gateway Protocol (BGP) Configuration
#
# BGP is used within the tunnel to exchange prefixes between the
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
# Virtual Private Gateway and your Customer Gateway. The Virtual Private Gateway
# will announce the prefix corresponding to your VPC.
#
# The BGP timers are adjusted to provide more rapid detection of outages.
#
# The local BGP Autonomous System Number (ASN) (YOUR_BGP_ASN) is configured
# as part of your Customer Gateway. If the ASN must be changed, the
# Customer Gateway and VPN Connection will need to be recreated with AWS.
#
bgp use on
bgp autonomous-system YOUR_BGP_ASN
bgp neighbor 1 7224 169.254.255.1 hold-time=30 local-address=169.254.255.2

# To advertise additional prefixes to Amazon VPC, copy the statement and
# identify the prefix you wish to advertise. Make sure the
# prefix is present in the routing table of the device with a valid next-hop.

bgp import filter 1 equal 0.0.0.0/0
bgp import 7224 static filter 1
bgp configure refresh

IKE

# -----
# IPsec Tunnel #2
# -----

# #1: Internet Key Exchange (IKE) Configuration
#
# A policy is established for the supported ISAKMP encryption,
# authentication, Diffie-Hellman, lifetime, and key parameters.
#
tunnel select 2
ipsec ike encryption 2 aes-cbc
ipsec ike group 2 modp1024
ipsec ike hash 2 sha

# The ISAKMP keyring stores the Pre Shared Key used to authenticate the
# tunnel endpoints.
#
ipsec ike pre-shared-key 2 text plain-text-password2

IPsec

# #2: IPsec Configuration

# The IPsec policy defines the encryption, authentication, and IPsec
# mode parameters.

# Note that there are a global list of IPsec policies, each identified by
# sequence number. This policy is defined as #201, which may conflict with
# an existing policy using the same number. If so, we recommend changing
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

```
# the sequence number to avoid conflicts.
#

ipsec tunnel 201
ipsec sa policy 201 2 esp aes-cbc sha-hmac

# The IPsec profile references the IPsec policy and further defines
# the Diffie-Hellman group and security association lifetime.

ipsec ike duration ipsec-sa 2 3600
ipsec ike pfs 2 on

# Additional parameters of the IPsec configuration are set here. Note that
# these parameters are global and therefore impact other IPsec
# associations.
# This option instructs the router to clear the "Don't Fragment"
# bit from packets that carry this bit and yet must be fragmented, enabling
# them to be fragmented.
#
ipsec tunnel outer df-bit clear

# This option enables IPsec Dead Peer Detection, which causes periodic
# messages to be sent to ensure a Security Association remains operational.

ipsec ike keepalive
```

**Tunnel**

```
# -----
----
# #3: Tunnel Interface Configuration
#
# A tunnel interface is configured to be the logical interface associated
# with the tunnel. All traffic routed to the tunnel interface will be
# encrypted and transmitted to the VPC. Similarly, traffic from the VPC
# will be logically received on this interface.
#
# Association with the IPsec security association is done through the
# "tunnel protection" command.
#
# The address of the interface is configured with the setup for your
# Customer Gateway. If the address changes, the Customer Gateway and VPN
# Connection must be recreated with Amazon VPC.
#
ipsec ike local address 2 YOUR_LOCAL_NETWORK_ADDRESS
ipsec ike remote address 2 72.21.209.193
ip tunnel address 169.254.255.6/30
ip tunnel remote address 169.254.255.5

# This option causes the router to reduce the Maximum Segment Size of
# TCP packets to prevent packet fragmentation

ip tunnel tcp mss limit 1396
tunnel enable 2
no tunnel select 2
ipsec auto refresh on
```

BGP

```
# -----  
-----  
# #4: Border Gateway Protocol (BGP) Configuration  
#  
# BGP is used within the tunnel to exchange prefixes between the  
# Virtual Private Gateway and your Customer Gateway. The Virtual Private Gateway  
# will announce the prefix corresponding to your VPC.  
#  
# The BGP timers are adjusted to provide more rapid detection of outages.  
#  
# The local BGP Autonomous System Number (ASN) (YOUR_BGP_ASN) is configured  
# as part of your Customer Gateway. If the ASN must be changed, the  
# Customer Gateway and VPN Connection will need to be recreated with AWS.  
#  
bgp use on  
bgp autonomous-system YOUR_BGP_ASN  
bgp neighbor 1 7224 169.254.255.5 hold-time=30 local-address=169.254.255.6  
  
# To advertise additional prefixes to Amazon VPC, copy the statement and  
# identify the prefix you wish to advertise. Make sure the  
# prefix is present in the routing table of the device with a valid next-hop.  
  
bgp import filter 1 equal 0.0.0.0/0  
bgp import 7224 static filter 1  
bgp configure refresh
```

## How to Test the Customer Gateway Configuration

You must first test the gateway configuration for each tunnel.

### To test the customer gateway configuration for each tunnel

1. On your customer gateway, determine if the BGP status is *Active*. It takes approximately 30 seconds for a BGP peering to become active.
2. Ensure that the customer gateway is advertising a route to the virtual private gateway. The route may be the default route (0.0.0.0/0) or a more specific route you prefer.

When properly established, your BGP peering should be receiving one route from the virtual private gateway corresponding to the prefix that your VPC integration team specified for the VPC (e.g., 10.0.0.0/24). If the BGP peering is established, you are receiving a prefix, and you are advertising a prefix, your tunnel is configured correctly. Make sure both tunnels are in this state.

Next you must test the connectivity for each tunnel.



### Important

For the connectivity test to work, you must configure any security group or network ACL in your VPC that filters traffic to the instance to allow inbound and outbound ICMP traffic.

### To test the end-to-end connectivity of each tunnel

1. Launch an instance of one of the Amazon Linux AMIs into your VPC. They're available in the Quick Start menu when you use the **Request Instances Wizard** in the AWS Management Console (for more information, see the [Amazon Virtual Private Cloud Getting Started Guide](#)).
2. After the instance is running, get its private IP address (e.g., 10.0.0.4). The console displays the address as part of the instance's details.
3. On a system in your home network, use the ping command with the instance's IP address. Make sure the computer you ping from is behind the customer gateway. A successful response should be similar to the following:

```
PROMPT> ping 10.0.0.4
Pinging 10.0.0.4 with 32 bytes of data:

Reply from 10.0.0.4: bytes=32 time<1ms TTL=128
Reply from 10.0.0.4: bytes=32 time<1ms TTL=128
Reply from 10.0.0.4: bytes=32 time<1ms TTL=128

Ping statistics for 10.0.0.4:
    Packets: Sent = 3, Received = 3, Lost = 0 (0% loss),

Approximate round trip times in milliseconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
```



### Note

If you ping an instance from your customer gateway router, ensure you are sourcing ping messages from an internal IP address, not a tunnel IP address. Some AMIs will not respond to ping messages from the tunnel IP addresses.

If your tunnels do not test successfully, see [Troubleshooting \(p. 61\)](#).

# Example: Generic Customer Gateway

---

## Topics


- [A High-Level View of the Customer Gateway \(p. 54\)](#)
- [A Detailed View of the Customer Gateway and an Example Configuration \(p. 54\)](#)
- [How to Test the Customer Gateway Configuration \(p. 59\)](#)

If your customer gateway isn't one of the types discussed earlier in this guide, your integration team will provide you with generic information that you can use to configure your customer gateway. This section contains an example of that information.

Two diagrams accompany the example configuration: The first diagram shows the high-level layout of the customer gateway, the second diagram supplies details that match the example configuration. You should take the real configuration information that your integration team gives you and apply it to your customer gateway.

## A High-Level View of the Customer Gateway

The following diagram shows the general details of your customer gateway. Note that the VPN connection consists of two separate tunnels: *Tunnel #1* and *Tunnel #2*. Two redundant tunnels provide an increased availability in the case of a device failure.



## A Detailed View of the Customer Gateway and an Example Configuration

The diagram in this section gives you a detailed illustration of an example generic customer gateway. After the diagram is a corresponding example of the configuration information you should get from your integration team. It contains a set of information for each of the two tunnels you must configure.

In addition, the example configuration refers to two items that you must provide:


- **YOUR\_UPLINK\_ADDRESS**—The IP address for the Internet-routable external interface on the customer gateway (which must be static and can't be behind a device performing NAT)

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

- **YOUR\_BGP\_ASN**—The customer gateway's BGP ASN

The example configuration includes several dummy values we're using to help you understand how configuration works. For example, we're using dummy values for the VPN connection ID (44a8938f), virtual private gateway ID (8db04f81), the IP addresses (e.g., 72.21.209.\*, 169.254.255.\*), and the remote ASN (7224). The actual configuration information you get will have real values in place of those dummy values.

In the following diagram and example configuration the items highlighted in red *italic* need to be replaced with values that apply to your own particular situation.



```

Amazon Web Services
Virtual Private Cloud

VPN Connection Configuration
=====
AWS utilizes unique identifiers to manipulate the configuration of
a VPN Connection. Each VPN Connection is assigned a VPN identifier
and is associated with two other identifiers, namely the
Customer Gateway Identifier and the Virtual Private Gateway Identifier.

Your VPN Connection ID           : vpn-44a8938f
Your Virtual Private Gateway ID  : vgw-8db04f81
Your Customer Gateway ID        : cgw-b4dc3961

A VPN Connection consists of a pair of IPsec tunnel security associations (SAs).

```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

It is important that both tunnel security associations be configured.

IPsec Tunnel #1

=====

**IKE**

#1: Internet Key Exchange Configuration

Configure the IKE SA as follows

- Authentication Method : Pre-Shared Key
- Pre-Shared Key : plain-text-password1
- Authentication Algorithm : sha1
- Encryption Algorithm : aes-128-cbc
- Lifetime : 28800 seconds
- Phase 1 Negotiation Mode : main
- Perfect Forward Secrecy : Diffie-Hellman Group 2

**IPsec**

#2: IPsec Configuration

Configure the IPsec SA as follows:

- Protocol : esp
- Authentication Algorithm : hmac-sha1-96
- Encryption Algorithm : aes-128-cbc
- Lifetime : 3600 seconds
- Mode : tunnel
- Perfect Forward Secrecy : Diffie-Hellman Group 2

IPsec Dead Peer Detection (DPD) will be enabled on the AWS Endpoint. We recommend configuring DPD on your endpoint as follows:

- DPD Interval : 10
- DPD Retries : 3

IPsec ESP (Encapsulating Security Payload) inserts additional headers to transmit packets. These headers require additional space, which reduces the amount of space available to transmit application data. To limit the impact of this behavior, we recommend the following configuration on your Customer Gateway:

- TCP MSS Adjustment : 1396 bytes
- Clear Don't Fragment Bit : enabled
- Fragmentation : Before encryption

**Tunnel**

#3: Tunnel Interface Configuration

Your Customer Gateway must be configured with a tunnel interface that is associated with the IPsec tunnel. All traffic transmitted to the tunnel interface is encrypted and transmitted to the Virtual Private Gateway.

Additionally, the Virtual Private Gateway and Customer Gateway establish the BGP peering from your tunnel interface.

The Customer Gateway and Virtual Private Gateway each have two addresses that relate

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

to this IPsec tunnel. Each contains an outside address, upon which encrypted traffic is exchanged. Each also contain an inside address associated with the tunnel interface.

The Customer Gateway outside IP address was provided when the Customer Gateway was created. Changing the IP address requires the creation of a new Customer Gateway.

The Customer Gateway inside IP address should be configured on your tunnel interface.

Outside IP Addresses:

- Customer Gateway: : YOUR\_UPLINK\_ADDRESS
- Virtual Private Gateway : 72.21.209.193

Inside IP Addresses

- Customer Gateway : 169.254.255.6/30
- Virtual Private Gateway : 169.254.255.5/30

Configure your tunnel to fragment at the optimal size:

- Tunnel interface MTU : 1436 bytes

**BGP**

#4: Border Gateway Protocol (BGP) Configuration:

The Border Gateway Protocol (BGPv4) is used within the tunnel, between the inside IP addresses, to exchange routes from the VPC to your home network. Each BGP router has an Autonomous System Number (ASN). Your ASN was provided to AWS when the Customer Gateway was created.

BGP Configuration Options:

- Customer Gateway ASN : YOUR\_BGP\_ASN
- Virtual Private Gateway ASN : 7224
- Neighbor IP Address : 169.254.255.1
- Neighbor Hold Time : 30

Configure BGP to announce the default route (0.0.0.0/0) to the VPN Connection Gateway. The Virtual Private Gateway will announce prefixes to your Customer Gateway based upon the prefixes assigned in the creation of the VPC.

IPsec Tunnel #2

=====

**IKE**

#1: Internet Key Exchange Configuration

Configure the IKE SA as follows

- Authentication Method : Pre-Shared Key
- Pre-Shared Key : plain-text-password2
- Authentication Algorithm : sha1
- Encryption Algorithm : aes-128-cbc
- Lifetime : 28800 seconds
- Phase 1 Negotiation Mode : main
- Perfect Forward Secrecy : Diffie-Hellman Group 2

**IPsec**

**Amazon Virtual Private Cloud Network Administrator  
Guide  
A Detailed View of the Customer Gateway and an  
Example Configuration**

#2: IPsec Configuration

Configure the IPsec SA as follows:

- Protocol : esp
- Authentication Algorithm : hmac-sha1-96
- Encryption Algorithm : aes-128-cbc
- Lifetime : 3600 seconds
- Mode : tunnel
- Perfect Forward Secrecy : Diffie-Hellman Group 2

IPsec Dead Peer Detection (DPD) will be enabled on the AWS Endpoint. We recommend configuring DPD on your endpoint as follows:

- DPD Interval : 10
- DPD Retries : 3

IPsec ESP (Encapsulating Security Payload) inserts additional headers to transmit packets. These headers require additional space, which reduces the amount of space available to transmit application data. To limit the impact of this behavior, we recommend the following configuration on your Customer Gateway:

- TCP MSS Adjustment : 1396 bytes
- Clear Don't Fragment Bit : enabled
- Fragmentation : Before encryption

**Tunnel**

#3: Tunnel Interface Configuration

Your Customer Gateway must be configured with a tunnel interface that is associated with the IPsec tunnel. All traffic transmitted to the tunnel interface is encrypted and transmitted to the Virtual Private Gateway.

Additionally, the Virtual Private Gateway and Customer Gateway establish the BGP peering from your tunnel interface.

The Customer Gateway and Virtual Private Gateway each have two addresses that relate to this IPsec tunnel. Each contains an outside address, upon which encrypted traffic is exchanged. Each also contain an inside address associated with the tunnel interface.

The Customer Gateway outside IP address was provided when the Customer Gateway was created. Changing the IP address requires the creation of a new Customer Gateway.

The Customer Gateway inside IP address should be configured on your tunnel interface.

Outside IP Addresses:

- Customer Gateway : YOUR\_UPLINK\_ADDRESS
- Virtual Private Gateway : 72.21.209.193

Inside IP Addresses

- Customer Gateway : 169.254.255.6/30
- Virtual Private Gateway : 169.254.255.5/30

Configure your tunnel to fragment at the optimal size:

```
- Tunnel interface MTU      : 1436 bytes
```

#### BGP

```
#4: Border Gateway Protocol (BGP) Configuration:
```

The Border Gateway Protocol (BGPv4) is used within the tunnel, between the inside IP addresses, to exchange routes from the VPC to your home network. Each BGP router has an Autonomous System Number (ASN). Your ASN was provided to AWS when the Customer Gateway was created.

BGP Configuration Options:

```
- Customer Gateway ASN      : YOUR_BGP_ASN
- Virtual Private Gateway ASN : 7224
- Neighbor IP Address       : 169.254.255.5
- Neighbor Hold Time        : 30
```

Configure BGP to announce the default route (0.0.0.0/0) to the VPN Connection Gateway. The Virtual Private Gateway will announce prefixes to your Customer Gateway based upon the prefixes assigned in the creation of the VPC.

Additional Notes and Questions

=====

```
- Amazon Virtual Private Cloud Getting Started Guide:
http://docs.amazonwebservices.com/AWSVPC/latest/GettingStartedGuide
- Amazon Virtual Private Cloud Network Administrator Guide:
http://docs.amazonwebservices.com/AWSVPC/latest/NetworkAdminGuide
```

## How to Test the Customer Gateway Configuration

You must first test the gateway configuration for each tunnel.

### To test the customer gateway configuration for each tunnel

1. On your customer gateway, determine if the BGP status is *Active*. It takes approximately 30 seconds for a BGP peering to become active.
2. Ensure that the customer gateway is advertising a route to the virtual private gateway. The route may be the default route (0.0.0.0/0) or a more specific route you prefer.

When properly established, your BGP peering should be receiving one route from the virtual private gateway corresponding to the prefix that your VPC integration team specified for the VPC (e.g., 10.0.0.0/24). If the BGP peering is established, you are receiving a prefix, and you are advertising a prefix, your tunnel is configured correctly. Make sure both tunnels are in this state.

Next you must test the connectivity for each tunnel.



### Important

For the connectivity test to work, you must configure any security group or network ACL in your VPC that filters traffic to the instance to allow inbound and outbound ICMP traffic.

### To test the end-to-end connectivity of each tunnel

1. Launch an instance of one of the Amazon Linux AMIs into your VPC. They're available in the Quick Start menu when you use the **Request Instances Wizard** in the AWS Management Console (for more information, see the [Amazon Virtual Private Cloud Getting Started Guide](#)).
2. After the instance is running, get its private IP address (e.g., 10.0.0.4). The console displays the address as part of the instance's details.
3. On a system in your home network, use the ping command with the instance's IP address. Make sure the computer you ping from is behind the customer gateway. A successful response should be similar to the following:

```
PROMPT> ping 10.0.0.4
Pinging 10.0.0.4 with 32 bytes of data:

Reply from 10.0.0.4: bytes=32 time<1ms TTL=128
Reply from 10.0.0.4: bytes=32 time<1ms TTL=128
Reply from 10.0.0.4: bytes=32 time<1ms TTL=128

Ping statistics for 10.0.0.4:
    Packets: Sent = 3, Received = 3, Lost = 0 (0% loss),

Approximate round trip times in milliseconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
```



#### Note

If you ping an instance from your customer gateway router, ensure you are sourcing ping messages from an internal IP address, not a tunnel IP address. Some AMIs will not respond to ping messages from the tunnel IP addresses.

If your tunnels do not test successfully, see [Troubleshooting \(p. 61\)](#).

# Troubleshooting

---

## Topics

- [Troubleshooting Cisco IOS Customer Gateway Connectivity \(p. 61\)](#)
- [Troubleshooting Juniper JunOS Customer Gateway Connectivity \(p. 66\)](#)
- [Troubleshooting Juniper ScreenOS Customer Gateway Connectivity \(p. 69\)](#)
- [Troubleshooting Yamaha Customer Gateway Connectivity \(p. 72\)](#)
- [Troubleshooting Generic Device Customer Gateway Connectivity \(p. 75\)](#)

This section contains troubleshooting information to use if your tunnels aren't in the correct state when you test your customer gateway (for general testing instructions applicable to all customer gateways, see [How to Test the Customer Gateway Configuration \(p. 59\)](#)).

## Troubleshooting Cisco IOS Customer Gateway Connectivity

When you troubleshoot the connectivity of a Cisco customer gateway you need to consider four things: IKE, IPsec, tunnel, and BGP. You can troubleshoot these areas any order, but we recommend that you start with IKE (at the bottom of the network stack) and move up.

### IKE

Use the following command. The response shows a customer gateway with IKE configured correctly.

```
router# show crypto isakmp sa
IPv4 Crypto ISAKMP SA
dst          src          state          conn-id slot status
192.168.37.160 72.21.209.193 QM_IDLE        2001    0 ACTIVE
192.168.37.160 72.21.209.225 QM_IDLE        2002    0 ACTIVE
```

You should see one or more lines containing a *src* of the Remote Gateway specified in the tunnels. The *state* should be *QM\_IDLE* and *status* should be *ACTIVE*. The absence of an entry, or any entry in another indicate that IKE is not configured properly.

For further troubleshooting, run the following commands to enable log messages that provide diagnostic information.

```
router# term mon
router# debug crypto isakmp
```

To disable debugging, use the following command.

```
router# no debug crypto isakmp
```

## IPsec

Use the following command. The response shows a customer gateway with IPsec configured correctly.

```
router# show crypto ipsec sa
interface: Tunnell
  Crypto map tag: Tunnell-head-0, local addr 192.168.37.160

protected vrf: (none)
local ident (addr/mask/prot/port): (0.0.0.0/0.0.0.0/0/0)
remote ident (addr/mask/prot/port): (0.0.0.0/0.0.0.0/0/0)
current_peer 72.21.209.225 port 500
  PERMIT, flags={origin_is_acl,}
  #pkts encaps: 149, #pkts encrypt: 149, #pkts digest: 149
  #pkts decaps: 146, #pkts decrypt: 146, #pkts verify: 146
  #pkts compressed: 0, #pkts decompressed: 0
  #pkts not compressed: 0, #pkts compr. failed: 0
  #pkts not decompressed: 0, #pkts decompress failed: 0
  #send errors 0, #recv errors 0

local crypto endpt.: 174.78.144.73, remote crypto endpt.: 72.21.209.225
path mtu 1500, ip mtu 1500, ip mtu idb FastEthernet0
current outbound spi: 0xB8357C22(3090512930)

inbound esp sas:
  spi: 0x6ADB173(112046451)
    transform: esp-aes esp-sha-hmac ,
    in use settings ={Tunnel, }
    conn id: 1, flow_id: Motorola SEC 2.0:1, crypto map: Tunnell-head-0
    sa timing: remaining key lifetime (k/sec): (4467148/3189)
    IV size: 16 bytes
    replay detection support: Y   replay window size: 128
    Status: ACTIVE

inbound ah sas:

inbound pcp sas:

outbound esp sas:
  spi: 0xB8357C22(3090512930)
    transform: esp-aes esp-sha-hmac ,
    in use settings ={Tunnel, }
    conn id: 2, flow_id: Motorola SEC 2.0:2, crypto map: Tunnell-head-0
    sa timing: remaining key lifetime (k/sec): (4467148/3189)
    IV size: 16 bytes
```

**Amazon Virtual Private Cloud Network Administrator  
Guide  
IPsec**

---

```
    replay detection support: Y   replay window size: 128
    Status: ACTIVE

outbound ah sas:

outbound pcp sas:

interface: Tunnel2
    Crypto map tag: Tunnel2-head-0, local addr 174.78.144.73

protected vrf: (none)
local ident (addr/mask/prot/port): (0.0.0.0/0.0.0.0/0/0)
remote ident (addr/mask/prot/port): (0.0.0.0/0.0.0.0/0/0)
current_peer 72.21.209.193 port 500
    PERMIT, flags={origin_is_acl,}
#pkts encaps: 26, #pkts encrypt: 26, #pkts digest: 26
#pkts decaps: 24, #pkts decrypt: 24, #pkts verify: 24
#pkts compressed: 0, #pkts decompressed: 0
#pkts not compressed: 0, #pkts compr. failed: 0
#pkts not decompressed: 0, #pkts decompress failed: 0
#send errors 0, #recv errors 0

local crypto endpt.: 174.78.144.73, remote crypto endpt.: 72.21.209.193
path mtu 1500, ip mtu 1500, ip mtu idb FastEthernet0
current outbound spi: 0xF59A3FF6(4120526838)

inbound esp sas:
    spi: 0xB6720137(3060924727)
    transform: esp-aes esp-sha-hmac ,
    in use settings ={Tunnel, }
    conn id: 3, flow_id: Motorola SEC 2.0:3, crypto map: Tunnel2-head-0
    sa timing: remaining key lifetime (k/sec): (4387273/3492)
    IV size: 16 bytes
    replay detection support: Y   replay window size: 128
    Status: ACTIVE

inbound ah sas:

inbound pcp sas:

outbound esp sas:
    spi: 0xF59A3FF6(4120526838)
    transform: esp-aes esp-sha-hmac ,
    in use settings ={Tunnel, }
    conn id: 4, flow_id: Motorola SEC 2.0:4, crypto map: Tunnel2-head-0
    sa timing: remaining key lifetime (k/sec): (4387273/3492)
    IV size: 16 bytes
    replay detection support: Y   replay window size: 128
    Status: ACTIVE

outbound ah sas:

outbound pcp sas:
```

For each tunnel interface, you should see both an *inbound esp sas* and *outbound esp sas*. Assuming an SA is listed ("spi: 0xF95D2F3C", for example) and the *Status* is *ACTIVE*, IPsec is configured correctly.

For further troubleshooting, use the following command to enable debugging.

```
router# debug crypto ipsec
```

Use the following command to disable debugging.

```
router# no debug crypto ipsec
```

## Tunnel

First, check that you have the necessary firewall rules in place. For a list of the rules, see [If You Have a Firewall Between the Internet and Your Customer Gateway \(p. 10\)](#).

If your firewall rules are set up correctly, then continue troubleshooting with the following command.

```
router# show interfaces tun1
Tunnell is up, line protocol is up
  Hardware is Tunnel
  Internet address is 169.254.255.2/30
  MTU 17867 bytes, BW 100 Kbit/sec, DLY 50000 usec,
    reliability 255/255, txload 2/255, rxload 1/255
  Encapsulation TUNNEL, loopback not set
  Keepalive not set
  Tunnel source 174.78.144.73, destination 72.21.209.225
  Tunnel protocol/transport IPSEC/IP
  Tunnel TTL 255
  Tunnel transport MTU 1427 bytes
  Tunnel transmit bandwidth 8000 (kbps)
  Tunnel receive bandwidth 8000 (kbps)
  Tunnel protection via IPSec (profile "ipsec-vpn-92df3bfb-0")
  Last input never, output never, output hang never
  Last clearing of "show interface" counters never
  Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
  Queueing strategy: fifo
  Output queue: 0/0 (size/max)
  5 minute input rate 0 bits/sec, 1 packets/sec
  5 minute output rate 1000 bits/sec, 1 packets/sec
    407 packets input, 30010 bytes, 0 no buffer
    Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
```

Ensure the *line protocol* is up. Check that the tunnel source IP address, source interface and destination respectively match the tunnel configuration for the customer gateway outside IP address, interface, and virtual private gateway outside IP address. Ensure that *Tunnel protection via IPSec* is present. Make sure to run the command on both tunnel interfaces. To resolve any problems here, review the configuration.

Also use the following command, replacing 169.254.255.1 with the inside IP address of your virtual private gateway.

```
router# ping 169.254.255.1 df-bit size 1410

Type escape sequence to abort.
Sending 5, 1410-byte ICMP Echos to 169.254.255.1, timeout is 2 seconds:
Packet sent with the DF bit set
!!!!!
```

You should see 5 exclamation points.

For further troubleshooting, review the configuration.

## BGP

Use the following command.

```
router# show ip bgp summary
BGP router identifier 192.168.37.160, local AS number 65000
BGP table version is 8, main routing table version 8
2 network entries using 312 bytes of memory
2 path entries using 136 bytes of memory
3/1 BGP path/bestpath attribute entries using 444 bytes of memory
1 BGP AS-PATH entries using 24 bytes of memory
0 BGP route-map cache entries using 0 bytes of memory
0 BGP filter-list cache entries using 0 bytes of memory
Bitfield cache entries: current 1 (at peak 2) using 32 bytes of memory
BGP using 948 total bytes of memory
BGP activity 4/1 prefixes, 4/1 paths, scan interval 15 secs

Neighbor          V    AS MsgRcvd MsgSent   TblVer  InQ  OutQ Up/Down
State/PfxRcd
169.254.255.1    4  7224    363    323       8    0    0 00:54:21    1
169.254.255.5    4  7224    364    323       8    0    0 00:00:24    1
```

Here, both neighbors should be listed. For each, you should see a *State/PfxRcd* value of 1.

If the BGP peering is up, verify that your customer gateway router is advertising the default route (0.0.0.0/0) to the VPC.

```
router# show bgp all neighbors 169.254.255.1 advertised-routes
For address family: IPv4 Unicast
BGP table version is 3, local router ID is 174.78.144.73
Status codes: s suppressed, d damped, h history, * valid, > best, i - internal,
               r RIB-failure, S Stale
Origin codes: i - IGP, e - EGP, ? - incomplete

Originating default network 0.0.0.0

Network          Next Hop           Metric  LocPrf Weight Path
*> 10.120.0.0/16  169.254.255.1      100      0   7224   i

Total number of prefixes 1
```

Additionally, ensure that you're receiving the prefix corresponding to your VPC from the virtual private gateway.

```
router# show ip route bgp
      10.0.0.0/16 is subnetted, 1 subnets
B       10.255.0.0 [20/0] via 169.254.255.1, 00:00:20
```

For further troubleshooting, review the configuration.

## Virtual Private Gateway Attachment

Make sure your virtual private gateway is attached to your VPC. Your integration team does this with the AWS Management Console.

If you have questions or need further assistance, please use the [Amazon VPC Discussion Forums](#).

## Troubleshooting Juniper JunOS Customer Gateway Connectivity

When you troubleshoot the connectivity of a Juniper customer gateway you need to consider four things: IKE, IPsec, tunnel, and BGP. You can troubleshoot these areas in any order, but we recommend that you start with IKE (at the bottom of the network stack) and move up.

### IKE

Use the following command. The response shows a customer gateway with IKE configured correctly.

```
user@router> show security ike security-associations
Index  Remote Address  State  Initiator cookie  Responder cookie  Mode
4      72.21.209.225  UP     c4cd953602568b74  0d6d194993328b02  Main
3      72.21.209.193  UP     b8c8fb7dc68d9173  ca7cb0abaedeb4bb  Main
```

You should see one or more lines containing a Remote Address of the Remote Gateway specified in the tunnels. The *State* should be *UP*. The absence of an entry, or any entry in another state (such as *DOWN*) is an indication that IKE is not configured properly.

For further troubleshooting, enable the IKE trace options (as recommended in the example configuration information (see [Example: Juniper JunOS Device \(p. 23\)](#)). Then run the following command to print a variety of debugging messages to the screen.

```
user@router> monitor start kmd
```

From an external host, you can retrieve the entire log file with the following command.

```
scp username@router.hostname:/var/log/kmd
```

### IPsec

Use the following command. The response shows a customer gateway with IPsec configured correctly.

```
user@router> show security ipsec security-associations
Total active tunnels: 2
ID      Gateway          Port  Algorithm          SPI          Life:sec/kb  Mon  vsys
<131073 72.21.209.225    500   ESP:aes-128/sha1  df27aae4    326/ unlim  -   0
>131073 72.21.209.225    500   ESP:aes-128/sha1  5de29aa1    326/ unlim  -   0
<131074 72.21.209.193    500   ESP:aes-128/sha1  dd16c453    300/ unlim  -   0
>131074 72.21.209.193    500   ESP:aes-128/sha1  c1e0eb29    300/ unlim  -   0
```

Specifically, you should see at least two lines per Gateway address (corresponding to the Remote Gateway). Note the carets at the beginning of each line (< >) which indicate the direction of traffic for the particular entry. The output has separate lines for inbound traffic ("<", traffic from the virtual private gateway to this customer gateway) and outbound traffic (">").

For further troubleshooting, enable the IKE traceoptions (for more information, see the preceding section about IKE).

## Tunnel

First, double-check that you have the necessary firewall rules in place. For a list of the rules, see [If You Have a Firewall Between the Internet and Your Customer Gateway](#) (p. 10).

If your firewall rules are set up correctly, then continue troubleshooting with the following command.

```
user@router> show interfaces st0.1
Logical interface st0.1 (Index 70) (SNMP ifIndex 126)
  Flags: Point-To-Point SNMP-Traps Encapsulation: Secure-Tunnel
  Input packets : 8719
  Output packets: 41841
  Security: Zone: Trust
  Allowed host-inbound traffic : bgp ping ssh traceroute
  Protocol inet, MTU: 9192
  Flags: None
  Addresses, Flags: Is-Preferred Is-Primary
  Destination: 169.254.255.0/30, Local: 169.254.255.2
```

Make sure that the *Security: Zone* is correct, and that the *Local* address matches the customer gateway tunnel inside address.

Next, use the following command, replacing 169.254.255.1 with the inside IP address of your virtual private gateway. Your results should look like the response shown here.

```
user@router> ping 169.254.255.1 size 1410 do-not-fragment
PING 169.254.255.1 (169.254.255.1): 1410 data bytes
64 bytes from 169.254.255.1: icmp_seq=0 ttl=64 time=71.080 ms
64 bytes from 169.254.255.1: icmp_seq=1 ttl=64 time=70.585 ms
```

For further troubleshooting, review the configuration.

## BGP

Use the following command.

```
user@router> show bgp summary
Groups: 1 Peers: 2 Down peers: 0
Table          Tot Paths  Act Paths Suppressed    History  Damp State   Pending
inet.0         2          1          0             0        0        0
0
Peer           AS           InPkt    OutPkt    OutQ    Flaps Last Up/Dwn
State|#Active/Received/Accepted/Damped...
169.254.255.1 7224         9        10         0        0        1:00
1/1/1/0       0/0/0/0
169.254.255.5 7224         8         9         0        0         56
0/1/1/0       0/0/0/0
```

## Amazon Virtual Private Cloud Network Administrator Guide BGP

For further troubleshooting, use the following command, replacing 169.254.255.1 with the inside IP address of your virtual private gateway.

```
user@router> show bgp neighbor 169.254.255.1
Peer: 169.254.255.1+179 AS 7224 Local: 169.254.255.2+57175 AS 65000
  Type: External      State: Established      Flags: <ImportEval Sync>
  Last State: OpenConfirm  Last Event: RecvKeepAlive
  Last Error: None
  Export: [ EXPORT-DEFAULT ]
  Options: <Preference HoldTime PeerAS LocalAS Refresh>
  Holdtime: 30 Preference: 170 Local AS: 65000 Local System AS: 0
  Number of flaps: 0
  Peer ID: 169.254.255.1      Local ID: 10.50.0.10      Active Holdtime: 30
  Keepalive Interval: 10      Peer index: 0
  BFD: disabled, down
  Local Interface: st0.1
  NLRI for restart configured on peer: inet-unicast
  NLRI advertised by peer: inet-unicast
  NLRI for this session: inet-unicast
  Peer supports Refresh capability (2)
  Restart time configured on the peer: 120
  Stale routes from peer are kept for: 300
  Restart time requested by this peer: 120
  NLRI that peer supports restart for: inet-unicast
  NLRI that restart is negotiated for: inet-unicast
  NLRI of received end-of-rib markers: inet-unicast
  NLRI of all end-of-rib markers sent: inet-unicast
  Peer supports 4 byte AS extension (peer-as 7224)
  Table inet.0 Bit: 10000
    RIB State: BGP restart is complete
    Send state: in sync
    Active prefixes:          1
    Received prefixes:        1
    Accepted prefixes:        1
    Suppressed due to damping: 0
    Advertised prefixes:      1
  Last traffic (seconds): Received 4      Sent 8      Checked 4
  Input messages:  Total 24      Updates 2      Refreshes 0      Octets 505
  Output messages: Total 26      Updates 1      Refreshes 0      Octets 582
  Output Queue[0]: 0
```

Here you should see *Received prefixes* and *Advertised prefixes* listed at 1 each. This should be within the *Table inet.0* section.

If the *State* is not *Established*, check the *Last State* and *Last Error* for details of what is required to correct the problem.

If the BGP peering is up, verify that your customer gateway router is advertising the default route (0.0.0.0/0) to the VPC.

```
user@router> show route advertising-protocol bgp 169.254.255.1

inet.0: 10 destinations, 11 routes (10 active, 0 holddown, 0 hidden)
  Prefix          Nexthop          MED      Lclpref    AS path
* 0.0.0.0/0      Self              0         0          I
```

Additionally, ensure that you're receiving the prefix corresponding to your VPC from the virtual private gateway.

```
user@router> show route receive-protocol bgp 169.254.255.1

inet.0: 10 destinations, 11 routes (10 active, 0 holddown, 0 hidden)
  Prefix                Nexthop          MED      Lclpref   AS path
* 10.110.0.0/16         169.254.255.1   100      -         7224 I
```

## Virtual Private Gateway Attachment

Make sure your virtual private gateway is attached to your VPC. Your integration team does this with the AWS Management Console.

If you have questions or need further assistance, please use the [Amazon VPC Discussion Forums](#).

# Troubleshooting Juniper ScreenOS Customer Gateway Connectivity

When you troubleshoot the connectivity of a Juniper ScreenOS-based customer gateway you need to consider four things: IKE, IPsec, tunnel, and BGP. You can troubleshoot these areas in any order, but we recommend that you start with IKE (at the bottom of the network stack) and move up.

## IKE and IPsec

Use the following command. The response shows a customer gateway with IKE configured correctly.

```
ssg5-serial-> get sa
total configured sa: 2
HEX ID      Gateway      Port Algorithm      SPI      Life:sec kb Sta  PID
vsys
00000002<   72.21.209.225 500 esp:a128/sha1 80041ca4 3385 unlim A/-  -1 0
00000002>   72.21.209.225 500 esp:a128/sha1 8cdd274a 3385 unlim A/-  -1 0
00000001<   72.21.209.193 500 esp:a128/sha1 ecf0bec7 3580 unlim A/-  -1 0
00000001>   72.21.209.193 500 esp:a128/sha1 14bf7894 3580 unlim A/-  -1 0
```

You should see one or more lines containing a Remote Address of the Remote Gateway specified in the tunnels. The *Sta* should be A/- and the *SPI* should be a hexadecimal number other than 00000000. Entries in other states indicate that IKE is not configured properly.

For further troubleshooting, enable the IKE trace options (as recommended in the example configuration information (see [Example: Juniper ScreenOS Device \(p. 34\)](#))).

## Tunnel

First, double-check that you have the necessary firewall rules in place. For a list of the rules, see [If You Have a Firewall Between the Internet and Your Customer Gateway \(p. 10\)](#).

If your firewall rules are set up correctly, then continue troubleshooting with the following command.

```
ssg5-serial-> get interface tunnel.1
Interface tunnel.1:
description tunnel.1
number 20, if_info 1768, if_index 1, mode route
link ready
vsys Root, zone Trust, vr trust-vr
admin mtu 1500, operating mtu 1500, default mtu 1500
*ip 169.254.255.2/30
*manage ip 169.254.255.2
route-deny disable
bound vpn:
  IPSEC-1

Next-Hop Tunnel Binding table
Flag Status Next-Hop(IP)   tunnel-id  VPN

pmtu-v4 disabled
ping disabled, telnet disabled, SSH disabled, SNMP disabled
web disabled, ident-reset disabled, SSL disabled

OSPF disabled  BGP enabled  RIP disabled  RIPng disabled  mtrace disabled
PIM: not configured  IGMP not configured
NHRP disabled
bandwidth: physical 0kbps, configured egress [gbw 0kbps mbw 0kbps]
              configured ingress mbw 0kbps, current bw 0kbps
              total allocated gbw 0kbps
```

Make sure that you see *link:ready*, and that the *IP* address matches the customer gateway tunnel inside address.

Next, use the following command, replacing 169.254.255.1 with the inside IP address of your virtual private gateway. Your results should look like the response shown here.

```
ssg5-serial-> ping 169.254.255.1
Type escape sequence to abort

Sending 5, 100-byte ICMP Echos to 169.254.255.1, timeout is 1 seconds
!!!!
Success Rate is 100 percent (5/5), round-trip time min/avg/max=32/32/33 ms
```

For further troubleshooting, review the configuration.

## BGP

Use the following command.

```
ssg5-serial-> get vrouter trust-vr protocol bgp neighbor
Peer AS Remote IP      Local IP      Wt Status  State      ConnID Up/Down
-----
--
  7224 169.254.255.1    169.254.255.2  100 Enabled  ESTABLISH   10 00:01:01
  7224 169.254.255.5    169.254.255.6  100 Enabled  ESTABLISH   11 00:00:59
```

## Amazon Virtual Private Cloud Network Administrator Guide BGP

Both BGP peers should be listed as State: ESTABLISH, which means the BGP connection to the virtual private gateway is active.

For further troubleshooting, use the following command, replacing 169.254.255.1 with the inside IP address of your virtual private gateway.

```
ssg5-serial-> get vr trust-vr prot bgp neigh 169.254.255.1
peer: 169.254.255.1, remote AS: 7224, admin status: enable
type: EBGp, multihop: 0(disable), MED: node default(0)
connection state: ESTABLISH, connection id: 18 retry interval: node de
fault(120s), cur retry time 15s
configured hold time: node default(90s), configured keepalive: node default(30s)
configured adv-interval: default(30s)
designated local IP: n/a
local IP address/port: 169.254.255.2/13946, remote IP address/port:
169.254.255.1/179
router ID of peer: 169.254.255.1, remote AS: 7224
negotiated hold time: 30s, negotiated keepalive interval: 10s
route map in name: , route map out name:
weight: 100 (default)
self as next hop: disable
send default route to peer: disable
ignore default route from peer: disable
send community path attribute: no
reflector client: no
Neighbor Capabilities:
  Route refresh: advertised and received
  Address family IPv4 Unicast: advertised and received
force reconnect is disable
total messages to peer: 106, from peer: 106
update messages to peer: 6, from peer: 4
Tx queue length 0, Tx queue HWM: 1
route-refresh messages to peer: 0, from peer: 0
last reset 00:05:33 ago, due to BGP send Notification(Hold Timer Expired)(code
4 : subcode 0)
number of total successful connections: 4
connected: 2 minutes 6 seconds
Elapsed time since last update: 2 minutes 6 seconds
```

If the BGP peering is up, verify that your customer gateway router is advertising the default route (0.0.0.0/0) to the VPC. Note that this command applies to ScreenOS version 6.2.0 and higher.

```
ssg5-serial-> get vr trust-vr protocol bgp rib neighbor 169.254.255.1 advertised
i: IBGP route, e: EBGp route, >: best route, *: valid route
      Prefix          Nexthop      Wt  Pref  Med Orig  AS-Path
-----
>i          0.0.0.0/0          0.0.0.0 32768  100   0  IGP
Total IPv4 routes advertised: 1
```

Additionally, ensure that you're receiving the prefix corresponding to your VPC from the virtual private gateway. Note that this command applies to ScreenOS version 6.2.0 and higher.

```
ssg5-serial-> get vr trust-vr protocol bgp rib neighbor 169.254.255.1 received
i: IBGP route, e: EBGp route, >: best route, *: valid route
      Prefix          Nexthop      Wt  Pref  Med Orig  AS-Path
```

```
-----  
-----  
>e*      10.0.0.0/16  169.254.255.1  100  100  100  IGP  7224  
Total IPv4 routes received: 1
```

## Virtual Private Gateway Attachment

Make sure your virtual private gateway is attached to your VPC. Your integration team does this with the AWS Management Console.

If you have questions or need further assistance, please use the [Amazon VPC Discussion Forums](#).

# Troubleshooting Yamaha Customer Gateway Connectivity

When you troubleshoot the connectivity of a Yamaha customer gateway you need to consider four things: IKE, IPsec, tunnel, and BGP. You can troubleshoot these areas in any order, but we recommend that you start with IKE (at the bottom of the network stack) and move up.

## IKE

Use the following command. The response shows a customer gateway with IKE configured correctly.

```
# show ipsec sa gateway 1  
sgw  flags local-id                               remote-id      # of sa  
-----  
1    U K   YOUR_LOCAL_NETWORK_ADDRESS      72.21.209.225  i:2 s:1 r:1
```

You should see a line containing a *remote-id* of the Remote Gateway specified in the tunnels. You can list all the security associations (SAs) by omitting the tunnel number.

For further troubleshooting, run the following commands to enable DEBUG level log messages that provide diagnostic information.

```
# syslog debug on  
# ipsec ike log message-info payload-info key-info
```

To cancel the logged items, use the following command.

```
# no ipsec ike log  
# no syslog debug on
```

## IPsec

Use the following command. The response shows a customer gateway with IPsec configured correctly.

```
# show ipsec sa gateway 1 detail  
SA[1] Duration: 10675s
```

## Amazon Virtual Private Cloud Network Administrator Guide Tunnel

```
Local ID: YOUR_LOCAL_NETWORK_ADDRESS
Remote ID: 72.21.209.225
Protocol: IKE
Algorithm: AES-CBC, SHA-1, MODP 1024bit

SPI: 6b ce fd 8a d5 30 9b 02 0c f3 87 52 4a 87 6e 77
Key: ** ** ** ** ** (confidential) ** ** ** ** **

-----
SA[2] Duration: 1719s
Local ID: YOUR_LOCAL_NETWORK_ADDRESS
Remote ID: 72.21.209.225
Direction: send
Protocol: ESP (Mode: tunnel)
Algorithm: AES-CBC (for Auth.: HMAC-SHA)
SPI: a6 67 47 47
Key: ** ** ** ** ** (confidential) ** ** ** ** **

-----
SA[3] Duration: 1719s
Local ID: YOUR_LOCAL_NETWORK_ADDRESS
Remote ID: 72.21.209.225
Direction: receive
Protocol: ESP (Mode: tunnel)
Algorithm: AES-CBC (for Auth.: HMAC-SHA)
SPI: 6b 98 69 2b
Key: ** ** ** ** ** (confidential) ** ** ** ** **

-----
SA[4] Duration: 10681s
Local ID: YOUR_LOCAL_NETWORK_ADDRESS
Remote ID: 72.21.209.225
Protocol: IKE
Algorithm: AES-CBC, SHA-1, MODP 1024bit
SPI: e8 45 55 38 90 45 3f 67 a8 74 ca 71 ba bb 75 ee
Key: ** ** ** ** ** (confidential) ** ** ** ** **

-----
```

For each tunnel interface, you should see both *receive sas* and *send sas*.

For further troubleshooting, use the following command to enable debugging.

```
# syslog debug on
# ipsec ike log message-info payload-info key-info
```

Use the following command to disable debugging.

```
# no ipsec ike log
# no syslog debug on
```

## Tunnel

First, check that you have the necessary firewall rules in place. For a list of the rules, see [If You Have a Firewall Between the Internet and Your Customer Gateway \(p. 10\)](#).

If your firewall rules are set up correctly, then continue troubleshooting with the following command.

```
# show status tunnel 1
TUNNEL[1]:
Description:
  Interface type: IPsec
  Current status is Online.
  from 2011/08/15 18:19:45.
  5 hours 7 minutes 58 seconds connection.
  Received:      (IPv4) 3933 packets [244941 octets]
                 (IPv6) 0 packet [0 octet]
  Transmitted:  (IPv4) 3933 packets [241407 octets]
                 (IPv6) 0 packet [0 octet]
```

Ensure the *current status* is online. Also, ensure that *Interface type* is IPsec. Make sure to run the command on both tunnel interfaces. To resolve any problems here, review the configuration.

## BGP

Use the following command.

```
# show status bgp neighbor
BGP neighbor is 169.254.255.1, remote AS 7224, local AS 65000, external link
  BGP version 0, remote router ID 0.0.0.0
  BGP state = Active
  Last read 00:00:00, hold time is 0, keepalive interval is 0 seconds
  Received 0 messages, 0 notifications, 0 in queue
  Sent 0 messages, 0 notifications, 0 in queue
  Connection established 0; dropped 0
  Last reset never
Local host: unspecified
Foreign host: 169.254.255.1, Foreign port: 0

BGP neighbor is 169.254.255.5, remote AS 7224, local AS 65000, external link
  BGP version 0, remote router ID 0.0.0.0
  BGP state = Active
  Last read 00:00:00, hold time is 0, keepalive interval is 0 seconds
  Received 0 messages, 0 notifications, 0 in queue
  Sent 0 messages, 0 notifications, 0 in queue
  Connection established 0; dropped 0
  Last reset never
Local host: unspecified
Foreign host: 169.254.255.5, Foreign port:
```

Here, both neighbors should be listed. For each, you should see a *BGP state* value of Active.

If the BGP peering is up, verify that your customer gateway router is advertising the default route (0.0.0.0/0) to the VPC.

```
# show status bgp neighbor 169.254.255.1 advertised-routes
Total routes: 1
*: valid route
  Network          Next Hop          Metric LocPrf Path
* default          0.0.0.0           0      IGP
```

Additionally, ensure that you're receiving the prefix corresponding to your VPC from the virtual private gateway.

```
# show ip route
Destination      Gateway          Interface      Kind  Additional Info.
default          ***.***.***.*** LAN3(DHCP)     static
10.0.0.0/16      169.254.255.1  TUNNEL[1]     BGP   path=10124
```

For further troubleshooting, review the configuration.

## Virtual Private Gateway Attachment

Make sure your virtual private gateway is attached to your VPC. Your integration team does this with the AWS Management Console.

If you have questions or need further assistance, please use the [Amazon VPC Discussion Forums](#).

## Troubleshooting Generic Device Customer Gateway Connectivity

The following diagram and table provide general instructions for troubleshooting a customer gateway other than a Cisco IOS, Juniper JunOS, or Yamaha device.



### Tip

When troubleshooting problems, you might find it useful to enable the debug features of your gateway device. Consult your gateway device vendor for details.

**Amazon Virtual Private Cloud Network Administrator  
Guide  
Troubleshooting Generic Device Customer Gateway  
Connectivity**

<b>IKE</b>	<p>Determine if an IKE Security Association exists.</p> <p>An IKE security association is required to exchange keys that are used to establish the IPsec Security Association.</p> <p>If no IKE security association exists, review your IKE configuration settings. You must configure the encryption, authentication, perfect-forward-secrecy, and mode parameters as listed in the customer gateway configuration.</p> <p>If an IKE security association exists, move on to IPsec.</p>
<b>IPsec</b>	<p>Determine if an IPsec Security Association exists.</p> <p>An IPsec security association is the tunnel itself. Query your customer gateway to determine if an IPsec Security Association is active. Proper configuration of the IPsec SA is critical. You must configure the encryption, authentication, perfect-forward-secrecy, and mode parameters as listed in the customer gateway configuration.</p> <p>If no IPsec Security Association exists, review your IPsec configuration.</p> <p>If an IPsec Security Association exists, move on to the tunnel.</p>
<b>Tunnel</b>	<p>Confirm the required firewall rules are set up (for a list of the rules, see <a href="#">If You Have a Firewall Between the Internet and Your Customer Gateway (p. 10)</a>). If they are, move forward.</p> <p>Determine if there is IP connectivity via the tunnel.</p> <p>Each side of the tunnel has an IP address as specified in the customer gateway configuration. The virtual private gateway address is the address used as the BGP neighbor address. From your customer gateway, ping this address to determine if IP traffic is being properly encrypted and decrypted.</p> <p>If the ping isn't successful, review your tunnel interface configuration to ensure the proper IP address is configured.</p> <p>If the ping is successful, move on to BGP.</p>
<b>BGP</b>	<p>Determine if the BGP peering is active.</p> <p>For each tunnel, do the following:</p> <ul style="list-style-type: none"> <li>• On your customer gateway, determine if the BGP status is <i>Active</i> or <i>Established</i>. It may take approximately 30 seconds for a BGP peering to become active.</li> <li>• Ensure that the customer gateway is advertising the default route (0.0.0.0/0) to the virtual private gateway.</li> </ul> <p>If the tunnels are not in this state, review your BGP configuration.</p> <p>If the BGP peering is established, you are receiving a prefix, and you are advertising a prefix, your tunnel is configured correctly. Ensure both tunnels are in this state, and you're done.</p>
	<p>Make sure your virtual private gateway is attached to your VPC. Your integration team does this with the AWS Management Console.</p>

If you have questions or need further assistance, please use the [Amazon VPC Discussion Forums](#).

## Document History

---

This documentation is associated with the 2011-07-15 release of Amazon Virtual Private Cloud. This guide was last updated on 06 March 2012.

The following table describes the important changes since the last release of the Amazon VPC documentation set.

Change	Description	Release Date
AWS VPN CloudHub and redundant VPN connections	With this release, the network administrator's guide has been updated with information about AWS VPN CloudHub, which you can use to securely communicate from one site to another with or without a VPC, and updated with information about using redundant VPN connections to provide a fault-tolerant connection to your VPC.	29 September 2011
VPC Everywhere	With this release, the network administrator's guide has been rewritten to reflect the new features available in the 2011-07-15 API version.	03 August 2011
Added MTU Support Information	Added information about support for Maximum Transmission Unit (MTU). For more information, see the <i>Bind tunnel to logical interface (route-based VPN)</i> requirement in <a href="#">Requirements for Your Customer Gateway</a> (p. 8).	04 May 2011
Updates to Configuration Templates	Updated the configuration templates to include information about encrypting packages after fragmentation. Also removed information about VRF from the Cisco configuration and removed information about the routing instance (RI) from the Juniper JunOS configuration.	15 February 2011