
Getting Started with AWS

Computing Basics for Windows



Getting Started with AWS: Computing Basics for Windows

Copyright © 2014 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

The following are trademarks of Amazon Web Services, Inc.: Amazon, Amazon Web Services Design, AWS, Amazon CloudFront, Cloudfront, Amazon DevPay, DynamoDB, ElastiCache, Amazon EC2, Amazon Elastic Compute Cloud, Amazon Glacier, Kindle, Kindle Fire, AWS Marketplace Design, Mechanical Turk, Amazon Redshift, Amazon Route 53, Amazon S3, Amazon VPC. In addition, Amazon.com graphics, logos, page headers, button icons, scripts, and service names are trademarks, or trade dress of Amazon in the U.S. and/or other countries. Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon.

All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Getting Started with AWS Computing Basics for Windows

Overview	1
Getting Started	7
Step 1: Sign Up for the Service	8
Step 2: Install the Command Line Tools	8
Step 3: Find a Suitable AMI	9
Step 4: Launch an Instance	10
Step 5: Deploy Your Application	12
Connect to Your Amazon EC2 Instance from Windows	12
Start Your Website Using IIS Manager	13
Configure the Amazon EC2 Instance	14
Step 6: Create a Custom AMI	23
Step 7: Create an Elastic Load Balancer	23
Step 8: Update Your Amazon EC2 Security Group	30
Step 9: Launch Amazon EC2 Instances Using Auto Scaling	31
Step 10: Create a CloudWatch Alarm	35
Step 11: Clean Up	42
Delete Your CloudWatch Alarm	42
Delete Your Elastic Load Balancer	43
Terminate Your Amazon EC2 Instances in Your Auto Scaling Group	43
Terminate Your Instance	45
Delete a Key Pair	45
Delete an Amazon EC2 Security Group	46
Pricing	47
Amazon EC2 Cost Breakdown	47
Summing It All Up	50
How to Further Save Costs	51
Related Resources	54
Document History	56

Overview

When you deploy any type of application, you typically need to do the following:

- Set up a computer to run your application.
- Secure your application and resources.
- Set up your network for users to access your application.
- Scale your application.
- Monitor your application and resources.
- Ensure that your application is fault-tolerant.

This guide introduces you to several key AWS services and components that help address these basic needs. In this guide, you will learn more about what these key services are, why they are important in deploying a web application, and how to use them.

To help you learn about the key AWS services, we'll review an example architecture of a web application hosted on AWS, and we'll walk through the process of deploying DNN Platform. (DNN is an open-source content management system.) You can adapt this sample to your specific needs if you want. By the end of this walkthrough, you should be able to do the following:

- Sign up for AWS.
- Launch, connect, secure, and deploy DNN Platform to a computer in the cloud.
- Create a custom template of a computer containing the hardware, software, and configuration you need.
- Set up a load balancer to distribute traffic across multiple computers in the cloud.
- Scale your fleet of computers in the cloud.
- Monitor the health of your application and computers.
- Clean up your AWS resources.

For a deeper understanding of AWS best practices and the various options that AWS provides, we recommend that you read *Web Application Hosting: Best Practices* at [AWS Cloud Computing Whitepapers](#).

If you are looking for a quicker and easier way to deploy your web applications, you can use an application management service. AWS application management services help you leverage other AWS services without having to manage each of them separately and manually:

- [AWS Elastic Beanstalk](#) lets you focus on the code while the service manages the rest.

- [AWS OpsWorks](#) gives you the flexibility to define your own software stack and deploy, operate, and automate a variety of applications and architectures.

For additional information about deployment and resource management on AWS, go to [Deployment and Management on AWS](#).

If this guide is not exactly what you are looking for, you may want to check out the following documents:

- [Getting Started with AWS](#) — Provides information about Amazon Web Services, with helpful links for learning more.
- [Getting Started with AWS Free Usage Tier](#) — Provides information about how to get started with the free usage tier.
- [Hosting Websites on Amazon S3](#) in the *Amazon Simple Storage Service Developer Guide* — Provides a walkthrough in just a few steps of a static website deployment that does not require running an application.
- [Getting Started with AWS CloudFormation](#) in the *AWS CloudFormation User Guide* — Helps you quickly get started using an AWS CloudFormation WordPress blog sample template without needing to figure out the order in which AWS services need to be provisioned or worry about the subtleties of how to make those dependencies work.
- [Getting Started with AWS Web Application Hosting for Microsoft Windows](#) — Provides a more in-depth walkthrough that uses more services, such as Amazon Simple Storage Service (Amazon S3), Amazon CloudFront, Amazon Relational Database Service (Amazon RDS), and Amazon Route 53.
- [Amazon Elastic Compute Cloud Microsoft Windows Guide](#) — Provides information that helps you get started using Amazon EC2 instances that run the Microsoft Windows Server operating system.

Introduction to AWS

If you are responsible for running a web application, you face a variety of infrastructure and architecture issues for which AWS can give you easy, seamless, and cost-effective solutions. This section provides a list of Amazon Web Services and components, and it explains the value they add in meeting the challenges you'll face in this example solution. We break this down in to the following sections: computing resources, security, monitoring, networking, and fault-tolerance.

Computing Resources

When you deploy an on-premises solution, you need to buy a computer with an operating system, software, and hardware that match your needs. When you deploy your solution on Amazon Web Services, you select an Amazon Machine Image (AMI) and then use it to deploy a virtual server known as an Amazon Elastic Compute Cloud (EC2) instance. An AMI is a template that contains a software configuration (e.g., operating system, application server, and applications). For example, an AMI might contain all the software to act as a web server (e.g., Windows Server, IIS, and your website). A large selection of public AMIs is available from Amazon and the Amazon EC2 community. You can find an AMI that most closely matches your needs and then customize it. You can save this customized configuration to another AMI, which you can use to launch new Amazon EC2 instances whenever you need them.

Storage can be an integral part of an Amazon EC2 instance, or it can be an independent component whose lifetime is managed separately from the lifetime of the instance. There are AMIs for each storage strategy, and you will need to decide which type you want to use. When you launch your Amazon EC2 instances, you can store your root device data on Amazon Elastic Block Store (Amazon EBS) or the local instance store. Amazon Elastic Block Store (Amazon EBS) is a durable, block-level storage volume that you can attach to a single Amazon EC2 running instance. Amazon EBS volumes behave like raw, unformatted, external block devices you can attach. They persist independently from the running life of an Amazon EC2 instance. Alternatively, the local instance store is a temporary storage volume and

persists only during the life of the instance. You might use Amazon EBS-backed instances for web or database servers that keep state locally and require the data to be available even if the associated instance crashes. You might use Amazon instance-store backed instances to manage traffic on large web sites where each instance is a clone. This is an inexpensive way to launch instances where data is not stored to the root device. To summarize the two key differences between these AMIs:

- You can stop and restart an Amazon EBS-backed instance, but you can only run or terminate an Amazon EC2 instance store-backed instance.
- By default, any data on the instance store is lost if the instance fails or terminates. Data on Amazon EBS-backed instances is stored on an Amazon EBS volume, so no data is lost if the instance is terminated.

For more information about the differences between instance store-backed and Amazon EBS-backed instances, go to [Basics of Amazon EBS-Backed AMIs and Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

Security

Typically, after you buy a new computer you need to create a new password to access it. In AWS, a key pair is used to connect to your instance. After you connect to your instance, you'll change your password just as you would on your local computer. You'll use this password to sign in to your instance each time.

When you deploy your application, you'll want to secure your system. For an on-premises deployment, you would normally specify the ports and the protocols in which users can access your application. In AWS, you do the same thing. AWS has [security groups](#) that act like inbound network firewalls so you can decide who can connect to your Amazon EC2 instance over which ports.

Scaling

You may find that your application traffic varies during the day. For example, from 9 a.m. to 5 p.m., you may experience peak traffic; for the rest of the day, traffic may be much slower. As traffic levels change, it would be useful to continually adjust the number of computers running your application to changes in traffic. Auto Scaling can automatically launch and terminate instances on your behalf according to the policies that you set. If you have defined a baseline AMI, Auto Scaling launches new instances with the exact same configuration. Auto Scaling can also send you notifications when it adds or removes instances.

Monitoring

You need to stay aware of the current performance and state of your resources. If your resources are not in the appropriate state, can't handle the traffic load, or are sitting idle, you need to be alerted so you can take appropriate action. [Amazon CloudWatch](#) monitors AWS cloud resources and the applications you run on AWS. You can collect and track metrics, analyze the data, and react immediately to keep your applications and business running smoothly. You can use information from Amazon CloudWatch to take action on the policies that you set using Auto Scaling. For example, you can create an alarm to notify you if your CPU utilization exceeds 95%. If the threshold is exceeded, Amazon CloudWatch sends an alarm, and Auto Scaling takes action according to the policy that you set. In this example, Auto Scaling can launch a new instance to handle the increased load. Similarly, you could set an alarm that notifies you if your CPU utilization falls below a certain threshold. In that case, Auto Scaling could terminate an instance, saving you money.

You can monitor the status of your instances by viewing status checks and scheduled events for your instances. Automated status checks performed by Amazon EC2 detect whether specific issues are affecting your instances. The status check information, together with the data provided by Amazon CloudWatch, gives you detailed operational visibility into each of your instances.

You can also see the status of specific events scheduled for your instances. Scheduled events provide information about upcoming activities, such as rebooting or terminating an instance, that are planned for your instances, along with the scheduled start and end times of each event. To learn more about instance status, go to [Monitoring the Status of Your Instances](#) in the *Amazon Elastic Compute Cloud User Guide*.

Networking

If you require multiple computers to host your web application, you need to balance the traffic across those computers. [Elastic Load Balancing](#) provides this service in the same way that an on-premises load balancer does. You can associate a load balancer with an Auto Scaling group. As instances are launched and terminated, the load balancer automatically directs traffic to the running instances. Elastic Load Balancing also performs health checks on each instance. If an instance is not responding, the load balancer can automatically redirect traffic to the healthy instances.

AWS assigns a URL to your AWS resources, such as your Elastic Load Balancer and your Amazon EC2 instances; however, you may want a URL that is more specific and easy to remember, such as [www.example.com](#). To do so, you need to purchase a domain name from a domain registrar. After you purchase your domain name, you can use [Amazon Route 53](#) to map your domain name to your AWS deployment.

You may want to provision a private, isolated network. You can use [Amazon Virtual Private Cloud \(Amazon VPC\)](#) to provision a private, isolated section of the Amazon Web Services (AWS) cloud where you can launch AWS resources in a virtual network that you define. For example, if you are hosting a multitier web application, you may want to customize the network configuration so that your web servers are public facing and your database and application servers are in a private-facing subnet with no Internet access. The application servers and databases can't be directly accessed from the Internet, but they can still access the Internet over a NAT instance so they can, for example, download patches.

You can control access between the servers and subnets by using inbound and outbound packet filtering provided by network access control lists and security groups. Some other cases where you may want to use Amazon VPC include:

- Hosting scalable web applications in the AWS cloud that are connected to your data center
- Extending your corporate network into the cloud
- Disaster recovery

For information on how to get started using Amazon VPC, go to [Get Started with Amazon VPC](#) in the *Amazon Virtual Private Cloud Getting Started Guide*.

Fault Tolerance

To make your web application fault-tolerant, you need to consider deploying your computers in different physical locations. It can be expensive to maintain hardware in different physical locations for an on-premises solution. AWS offers resources in different Availability Zones and regions. Availability Zones are analogous to data centers. You can have multiple instances running in different Availability Zones so that if one Availability Zone becomes unavailable (e.g., due to a natural disaster), then all traffic would be routed to another Availability Zone. There are multiple Availability Zones in each region.

It's even more advantageous to spread your instances across Regions. If a region, including all of its Availability Zones, becomes completely unavailable, your traffic is routed to another region.

Summary

The following table summarizes the key challenges to developing a simple web application and the AWS services that address these challenges.

**Getting Started with AWS Computing Basics for
Windows
Summary**


Challenge	Amazon Web Services	Benefit
Need computers to run your application.	Amazon Elastic Compute Cloud (EC2)	Amazon EC2 runs the web server and application servers.
Incoming traffic needs to be evenly distributed across computers to maximize performance.	Elastic Load Balancing	Elastic Load Balancing supports health checks on hosts, distribution of traffic to Amazon EC2 instances across multiple Availability Zones, and dynamic addition and removal of Amazon EC2 hosts from the load-balancing rotation.
Servers need to be provisioned to handle peak capacity, but the unused cycles are wasted at other times.	Auto Scaling	Auto Scaling creates capacity groups of servers that can grow or shrink on demand.
Servers need to be monitored for performance and state	Amazon CloudWatch	Amazon CloudWatch reports metrics data for Amazon EC2 instances, and the metrics it gathers are used by Auto Scaling.
Applications may require persistent storage.	Amazon Elastic Block Store (Amazon EBS)	Amazon EBS provides a persistent file system for web and application servers.

The following table summarizes additional challenges to developing a simple web application and the AWS components that address these challenges.

Challenge	AWS Component	Benefit
Need a secure mechanism to connect to the computer.	Amazon Key Pair	A key pair is a security credential similar to a password, which you use to securely connect to your instance after the instance is running.
Need to provide security to protect application servers from outside malicious users.	Amazon Security Group	An Amazon Security Group gives you control over the protocols, ports, and source IP address ranges that are allowed to reach your Amazon EC2 instances.
Need to design with failover in mind.	Availability Zones	Availability Zones are distinct locations engineered to be insulated from failures in other Availability Zones. Each Availability Zone provides inexpensive, low-latency network connectivity to other Availability Zones in the same region.

Sample Architecture

The following diagram shows an example architecture that uses the AWS resources mentioned in the previous section.



As an example, we'll walk through a deployment of a simple web application. If you're doing something else, you can adapt this example architecture to your specific situation. In this diagram, Amazon EC2 instances in a security group run the application and web server. The Amazon EC2 Security Group acts as an exterior firewall for the Amazon EC2 instances. An Auto Scaling group maintains a fleet of Amazon EC2 instances that can be automatically added or removed in order to handle the presented load. This Auto Scaling group spans two Availability Zones to protect against potential failures in either Availability Zone. To ensure that traffic is distributed evenly among the Amazon EC2 instances, an Elastic Load Balancer is associated with the Auto Scaling group. If the Auto Scaling group launches or terminates instances to respond to load changes, the Elastic Load Balancer automatically adjusts accordingly.

For a step-by-step walkthrough of how to build out this architecture, see [Getting Started \(p. 7\)](#). This walkthrough will teach you how to do the following:

- Sign up for AWS.
- Launch, connect, and deploy DotNetDuke to an Amazon EC2 instance.
- Create a Custom AMI.
- Set up an Elastic Load Balancer to distribute traffic across your Amazon EC2 instances.
- Scale your fleet of instances automatically using Auto Scaling.
- Monitor your AWS resources using Amazon CloudWatch.
- Clean up your AWS resources.

Getting Started

Topics

- [Step 1: Sign Up for the Service \(p. 8\)](#)
- [Step 2: Install the Command Line Tools \(p. 8\)](#)
- [Step 3: Find a Suitable AMI \(p. 9\)](#)
- [Step 4: Launch an Instance \(p. 10\)](#)
- [Step 5: Deploy Your Application \(p. 12\)](#)
- [Step 6: Create a Custom AMI \(p. 23\)](#)
- [Step 7: Create an Elastic Load Balancer \(p. 23\)](#)
- [Step 8: Update Your Amazon EC2 Security Group \(p. 30\)](#)
- [Step 9: Launch Amazon EC2 Instances Using Auto Scaling \(p. 31\)](#)
- [Step 10: Create a CloudWatch Alarm \(p. 35\)](#)
- [Step 11: Clean Up \(p. 42\)](#)

Let's suppose you want to deploy DNN Platform, an open-source content management system (CMS). It's easy to get started, and for most of the tasks we can use the [AWS Management Console](#). In this topic, we'll walk through a series of steps to deploy your web application to AWS. There are many different ways you can go about deploying your web application. The approach that this walkthrough takes follows best practices and uses several of the core services so you can see how they work together.

Before you begin deploying DNN Platform using AWS, you'll need to sign up for an AWS account and install the Auto Scaling command line tools. Signing up for AWS gives you access to all of the services; however, you are charged only for what you use.

After you have signed up, you'll find a suitable AMI that meets your hardware and software needs. You'll use this AMI to launch an Amazon EC2 instance. When launching your Amazon EC2 instance, you'll create a new key pair and a security group. The security group sets rules for who can access the Amazon EC2 instance, and the key pair is necessary for connecting to your Amazon EC2 instance.

With your instance running and secured, you will finish installing the required software and then configure the DNN Platform application. To simplify launching new Amazon EC2 instances that are already configured, you'll create a custom AMI that will become your new baseline.

You'll then create an Elastic Load Balancer to distribute the traffic load across multiple instances and then update your security group to allow HTTP traffic from only your load balancer instead of from everyone. You create your Elastic Load Balancer before you launch your instances so that you can associate your

Auto Scaling group with your Elastic Load Balancer. That way, your load balancer can automatically stop routing traffic to any terminated instances, and it can start routing traffic to any newly launched instances.

At this point, you'll use Auto Scaling to launch your Amazon EC2 instances. You'll create an Auto Scaling policy that tells Auto Scaling when to increment or decrement the number of instances in your group.

Finally, you'll create a CloudWatch alarm that monitors the instances in your Auto Scaling group and tells the Auto Scaling group when to take action on that policy.

Because this is a sample deployment, you may want to terminate all the AWS resources that you have created. As soon as you terminate an AWS resource, you stop accruing charges for that resource.

Step 1: Sign Up for the Service

If you don't already have an AWS account, you'll need to get one. Your AWS account gives you access to all services, but you will be charged only for the resources that you use. For this example walkthrough, the charges will be minimal.

To sign up for AWS

1. Go to <http://aws.amazon.com> and click **Sign Up**.
2. Follow the on-screen instructions.

AWS notifies you by email when your account is active and available for you to use.

You use your AWS account to deploy and manage resources within AWS. If you give other people access to your resources, you will probably want to control who has access and what they can do. AWS Identity and Access Management (IAM) is a web service that controls access to your resources by other people. In IAM, you create users, which other people can use to obtain access and permissions that you define. For more information about IAM, go to [Using IAM](#).

Step 2: Install the Command Line Tools

We'll need to install some command line tools for Auto Scaling. Do this first to minimize your usage of billable services.


To install the Auto Scaling command line tools to your local computer, go to [Using the Command Line Tools](#) in the *Auto Scaling Developer Guide*. After you have installed the command line tools, try a couple of commands to make sure they work. For example, try typing the `as-cmd` command at the prompt.

```
PROMPT>as-cmd
```

This command returns a list of all the Auto Scaling commands and their descriptions. You should see something similar to the following illustration.

Getting Started with AWS Computing Basics for Windows

Step 3: Find a Suitable AMI



```
Start Command Prompt with Ruby
C:\Ruby192\AutoScaling-2011-01-01\AutoScaling-1.0.39.0\bin>as-cmd
Command Name      Description
-----
as-create-auto-scaling-group      Create a new auto scaling group
as-create-launch-config           Create a new launch config
as-create-or-update-trigger       Creates a new trigger or updates an existing trigger.
as-delete-auto-scaling-group      Delete the specified auto scaling group
as-delete-launch-config           Delete the specified launch configuration
as-delete-notification-configuration Delete the specified notification configuration
as-delete-policy                  Delete the specified policy
as-delete-scheduled-action       Delete the specified scheduled action
as-delete-trigger                 Delete a trigger.
as-describe-adjustment-types      Describes all policy adjustment types.
as-describe-auto-scaling-groups   Describes the specified auto scaling group(s)
as-describe-auto-scaling-instances Describes the specified auto scaling instance(s)
as-describe-auto-scaling-notification-types Describes all auto scaling notification types.
as-describe-launch-configs        Describe the specified launch configurations
as-describe-metric-collection-types Describes all metric colle... metric granularity types.
as-describe-notification-configurations Describes all notification... given auto-scaling groups
as-describe-policies              Describes the specified policy/policies
as-describe-process-types         Describes all scaling process types.
as-describe-scaling-activities    Describe a set of activiti...ties belonging to a group.
as-describe-scheduled-actions    Describes the specified scheduled action(s)
as-describe-triggers              Describes a trigger including its internal state.
as-disable-metrics-collection    Disable collection of AutoScaling group metrics
as-enable-metrics-collection      Enable collection of AutoScaling group metrics
as-execute-policy                 Executes the specified policy
as-put-notification-configuration Create or replace notifica...for the auto scaling group
as-put-scaling-policy             Creates or updates a scaling policy
as-put-scheduled-update-group-action Creates or updates a scheduled update group action
as-resume-processes               Resumes all suspended scal... given auto scaling group.
as-set-desired-capacity           Set the desired capacity of the auto scaling group
as-set-instance-health           Set the health of the instance
as-suspend-processes              Suspends all scaling proce... given auto scaling group.
as-terminate-instance-in-auto-scaling-group Terminate a given instance.
as-update-auto-scaling-group      Update specified auto scaling group
help
version                            Prints the version of the CLI tool and the API.

For help on a specific command, type '<commandname> --help'

C:\Ruby192\AutoScaling-2011-01-01\AutoScaling-1.0.39.0\bin>
```

After you have installed the command line tools, you can start creating your AWS resources. Move on to [Step 3: Find a Suitable AMI \(p. 9\)](#) to learn how to find a suitable AMI. You will use this AMI to launch your Amazon EC2 instance. It will also serve as a baseline for creating your own custom AMI.

Step 3: Find a Suitable AMI

An Amazon Machine Image (AMI) is similar to an imaged version of your server. Typically, you start from an Amazon provided base image, of which you launch an instance, configure the application and role specifics, and then bundle it into your own AMI for quick launching and scalability. This allows for the AMI to be preconfigured as a web server (e.g., Windows Server, IIS, and your web site), or as any other role.

A large selection of AMIs is available from Amazon and the Amazon EC2 community. For more information, go to [Amazon Machine Images \(AMIs\)](#) at the AWS website.

You can use the AWS Management Console (at <http://console.aws.amazon.com>) to search for AMIs that meet specific criteria and then launch instances of those AMIs. For example, you can view the AMIs Amazon has provided, AMIs the EC2 community has provided, or AMIs that use certain operating systems.

In this walkthrough, we will use an Amazon Windows AMI that has Windows Server 2008 R2 SP1, SQL Server Express 2008 R2, and IIS installed. To find one fitting these make sure you have an AMI with IIS installed, For more information about Windows AMIs, go to [Amazon Windows AMI Basics](#) in the *Amazon Elastic Compute Cloud Microsoft Windows Guide*.

To find a suitable AMI

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. Make sure that **US East (N. Virginia)** is selected in the region selector of the navigation bar.
3. In the navigation pane, click **AMIs**.

4. In the **Filter** lists, select **Public images**, then **Amazon images**, then **Windows**. This limits the display to AMIs that are provided by Amazon Web Services.
5. Select an AMI that is running Windows Server 2008 R2, IIS and SQL Express. To do that, you'll need to select an AMI and then read the **Description** tab below the list. With a suitable AMI selected, click **Launch**.

You will use this AMI as a baseline. Clicking **Launch** starts the launch wizard, which configures your instance and then launches it. In [Step 4: Launch an Instance \(p. 10\)](#), we will walk through the wizard.

Step 4: Launch an Instance

You are now ready to launch an Amazon EC2 instance using the AMI that you selected in the previous step. Launching an instance involves the following tasks:

- Configure the instance.
- Create a key pair.
- Create a security group.
- Launch the instance.

In the previous step, you selected an AMI and clicked **Launch**, which displays the launch wizard. However, EC2 provides other ways to launch an instance. If you click **Instances** in the left navigation pane and then click **Launch Instance**, the launch wizard appears.

Because we already selected an AMI in the previous step, the wizard appears on the second step, **Choose an Instance Type**.

Important

The instance you're about to launch will be live. You will incur the standard Amazon EC2 usage fees for the instance until you terminate it in the last task in this tutorial. If you complete this walkthrough in one session, the total charges will be minimal (typically less than a dollar). For more information about Amazon EC2 usage rates, go to the [Amazon EC2 product page](#).

To launch an Amazon EC2 instance

1. On the **Choose an Instance Type** page, select the **m1.large** instance type, and then click **Next: Configure Instance Details**.

Tip

If you can't find the m1.large instance type, ensure that you have selected the **All instances** category.

2. On the next pages of the wizard, accept the default settings and click **Next** until you get to the **Configure Security Group** page.
3. Create a security group:

A security group defines firewall rules for your instances. These rules specify which incoming network traffic should be delivered to your instance (e.g., accept web traffic on port 80). All other traffic is ignored. You can modify rules for a group at any time. The new rules are automatically enforced for all running instances. For more information about security groups, go to [Using Security Groups](#) in the *Amazon Elastic Compute Cloud (Amazon EC2)*.

Caution

By default, the launch wizard creates a security group that enables *all* IP addresses to access your instance over RDP. This is acceptable for the short exercise in this tutorial, but it's not secure for production environments. In production, you'll authorize only a specific IP address or range of addresses to access your instance.

**Getting Started with AWS Computing Basics for
Windows
Step 4: Launch an Instance**

- a. In the **Security group name** field, clear the default security group name and type **webappsecuritygroup**.
- b. In the **Description** field, you can clear the default description, and type a description of your choice.
- c. Ensure that the MS SQL and HTTP ports are open to traffic. If not, click **Add Rule**, and select them from the **Type** list.

Type	Protocol	Port Range	Source
MS SQL	TCP	1433	Anywhere 0.0.0.0/0
RDP	TCP	3389	Anywhere 0.0.0.0/0
HTTP	TCP	80	Anywhere 0.0.0.0/0

Add Rule

- d. Click **Review and Launch**.

The security group is created and assigned an ID (e.g., sg-48996e20). Your instance will be launched into this new security group.

4. Review your settings and click **Launch**. You'll be prompted to select or create a key pair. In this exercise, we'll create a new key pair in the next step.
5. Create a key pair:
 - a. Amazon EC2 instances created from a public AMI use a public/private key pair, rather than a password, for signing in. The public key is embedded in your instance. You use the private key to sign in securely without a password. After you create your own AMIs, you can choose other mechanisms to securely log in to your new instances.

Select **Create a new key pair**, and in the **Key pair name** box, type **mykeypair**. This will be the name of the private key file associated with the pair (with a `.pem` extension).

- b. Click **Download Key Pair**.

You're prompted to save the private key from the key pair to your system.

- c. Save the private key in a safe place on your system, and record the location where you saved it.

Important

You need the key pair file to be able to connect to your Amazon EC2 instance. You can't download the key pair file again, so if you lose it, you will not be able to connect to your instance.

- d. Select the acknowledgment check box, and click **Launch Instances**.
6. When a confirmation message appears, click the instance ID (*i*-xxxxxxx, the letter *i* followed by alphanumeric characters) in the message. It takes a short time for an instance to launch. While the instance is launching, its status will be shown as *pending*.

After a short period, your instance's status switches to *running*. To manually refresh the display at any time, you can click the refresh icon (two arrows). When your instance's status is *running*, you can connect to your instance and deploy your application.

7. Record the public DNS name for your instance:

**Getting Started with AWS Computing Basics for
Windows
Step 5: Deploy Your Application**

- Select the running instance, and note the public DNS address in the bottom pane. You will need it for the next task.



Step 5: Deploy Your Application

Topics

- [Connect to Your Amazon EC2 Instance from Windows \(p. 12\)](#)
- [Start Your Website Using IIS Manager \(p. 13\)](#)
- [Configure the Amazon EC2 Instance \(p. 14\)](#)

Now that you've launched your Amazon EC2 instance, it's time connect to it and deploy your application. In this step, you'll deploy DNN Platform.

Connect to Your Amazon EC2 Instance from Windows

To connect to a Windows instance, you must retrieve the initial password for the Administrator account and then use it with Windows Remote Desktop. You'll also need the contents of the private key file that you created (e.g., `mykeypair.pem`) in [Step 4: Launch an Instance \(p. 10\)](#).

Note

It can take up to 30 minutes to get the original password from the time you launched your Amazon EC2 instance.

To connect to your Windows instance

1. Sign in to the AWS Management Console and open the Amazon EC2 console at <https://console.aws.amazon.com/ec2>.
2. In the navigation pane, select **Instances**. Select your instance, and click **Connect**.
3. In the **Connect To Your Instance** dialog box, click **Get Password** (it will take a few minutes after the instance is launched before the password is available).

Note

You need to retrieve the password only on the first launch. After you connect to your instance, you should change your password and then use the new password when you sign in again.

4. Click **Browse** and navigate to the private key file you created when you launched the instance. Select the file and click **Open** to copy the entire contents of the file into contents box.
5. Click **Decrypt Password**. The console displays the default administrator password for the instance in the **Connect To Your Instance** dialog box, replacing the link to **Get Password** shown previously with the actual password.
6. Record the default administrator password, or copy it to the clipboard. You need this password to connect to the instance.

Getting Started with AWS Computing Basics for Windows

Start Your Website Using IIS Manager

- Click **Download Remote Desktop File**. Your browser prompts you to either open or save the .rdp file. Either option is fine. When you have finished, you can click **Close** to dismiss the **Connect To Your Instance** dialog box.

Note

Most Windows operating systems from Windows XP onward already include the Remote Desktop application. If you're using an earlier version of Windows, you can download the Remote Desktop application from the [Microsoft web site](#).

- If you opened the .rdp file, you'll see the **Remote Desktop Connection** dialog box. If you saved the .rdp file, navigate to your downloads directory, and double-click the .rdp file to display the dialog box. You may get a warning that the publisher of the remote connection is unknown. Click **Connect** to connect to your instance. You may get a warning that the security certificate could not be authenticated. Click **Yes** to continue.
- Log in to the instance as prompted, using `Administrator` as the user name and the default administrator password that you recorded or copied earlier.
- Create another user account on the instance, and then add it to the **Administrators** group. Another administrator account is a safeguard in case you forget your administrator password or have a problem with the Administrator account.


You can now work with your instance as you would any Windows Server computer. Move on to [Start Your Website Using IIS Manager \(p. 13\)](#) to connect to your website using IIS Manager.

Start Your Website Using IIS Manager

Before you move on to deploy DNN Platform, ensure that you can start your website using IIS Manager.

To start your website using IIS Manager

- From your Amazon EC2 instance, click **Start**. Click **Administrative Tools**, and then click **Internet Information Services (IIS) Manager**.
- Expand the `localhost` node.
- Expand the **Sites** node.



- Right-click **Default Web Site**, point to **Manage Web Site**, and then click **Start**. (It may already be running.)
- Launch a browser on your local computer. Into its address bar, paste the public DNS address of your Amazon EC2 instance that you recorded in [Step 4: Launch an Instance \(p. 10\)](#) to make certain that you can connect to the site.

Getting Started with AWS Computing Basics for Windows

Configure the Amazon EC2 Instance


After you have verified that your web server is working correctly, you can deploy DNN Platform to your Amazon EC2 instance.

Configure the Amazon EC2 Instance

In this topic, you will install the Microsoft Web Platform Installer and then install and configure DNN Platform on your Amazon EC2 instance.


Configure Server Manager Settings

1. In your Amazon EC2 instance, click **Start**. Click **Administrative Tools**, and then click **Server Manager**.
2. In the **Server Manager** application, in the **Security Information** panel, click **Configure IE ESC**.



3. In the **Internet Explorer Enhanced Security Configuration** box, under **Administrators**, click **Off**, and then click **OK**.
4. Close the **Server Manager**.
5. On the Amazon EC2 instance, open Internet Explorer. In the Internet Explorer web address box, type `http://www.iis.net/download/webdeploy`.
6. To install the latest version of Web Deploy, in the **Web Deploy** section, click **Install this extension**.

**Getting Started with AWS Computing Basics for
Windows
Configure the Amazon EC2 Instance**




7. If you are prompted, click **Run** to install the Web Platform Installer and install Web Deploy.


If the Web Platform Installer window appears, click **Install**. If the Web Platform Installer does not run, click the **Free Web Platform Installer** link near the top of the page and follow the instructions to download and install it. Then click **Products** at the top of the **Web Platform Installer** window and click **Add** for **Web Deploy** in the list of products. Click **Install**.

Getting Started with AWS Computing Basics for Windows

Configure the Amazon EC2 Instance




8. In the list of third-party application software, Microsoft products, and components appears, click **I Accept**. The Web Platform Installer begins to install the software.



9. When the installation is completed, click **Finish**. Next, you'll use the Web Platform Installer to install DNN Platform.


**Getting Started with AWS Computing Basics for
Windows
Configure the Amazon EC2 Instance**



To Install DNN Platform


1. At the top of the **Web Platform Installer** window, click **Applications**.
2. Navigate to the **DNN Platform** row, click **Add**, and then click **Install**.

**Getting Started with AWS Computing Basics for
Windows
Configure the Amazon EC2 Instance**




3. Make sure **SQL Server (Not Installed)** is selected as the database you want to install. Type a password for your SQL Server Express database in the **Password** box and the **Re-type Password** box. Click **Continue**.

**Getting Started with AWS Computing Basics for
Windows
Configure the Amazon EC2 Instance**



4. When the list of third-party application software, Microsoft products, and components appears, click **I Accept**.



It can take a few minutes for the installer to finish. When it does, you will be prompted to configure your new site.

**Getting Started with AWS Computing Basics for
Windows
Configure the Amazon EC2 Instance**

5. On the **Configure** page, accept all the default information and click **Continue**.

Web Platform Installer 4.6

PREREQUISITES INSTALL **CONFIGURE** FINISH

Web Site:
Default Web Site

'DNN Platform' application name:
dotnetnuke
http://localhost:80/dotnetnuke

Web Site Name:
Default Web Site

Physical path:
C:\inetpub\wwwroot


IP address: All Unassigned **Port:** 80

Host Name:
Example: localhost or application.contoso.com

Cancel Continue

6. When the installation is complete, click **Launch DNN Platform**.


**Getting Started with AWS Computing Basics for
Windows
Configure the Amazon EC2 Instance**



7. When the DNN Platform **Installation** page appears, do the following:
 - a. Follow these steps to open the **Advanced Settings** dialog box and set the **Identity** of the DNN Platform application pool to **NetworkService**:
 - i. In IIS Manager, expand the tree in the pane on the left and click **Application Pools**.
 - ii. In the center pane, right-click **dotnetnuke**, and then click **Advanced Settings**.
 - iii. Under **Process Model**, click **Identity** and then click ... to open the **Application Pool Identity** dialog. For **Built-in account**, choose **NetworkService** and click **OK**.

Getting Started with AWS Computing Basics for Windows

Configure the Amazon EC2 Instance



- iv. In the **Advanced Settings** dialog box, click **OK**.
- b. On the DNN Platform **Installation** page, enter a **Username**, **Password**, and **Website Information**. Accept the remaining defaults, and then click **Continue**.

DNN

Installation

1 Enter Your Account Information → 2 Proceed with Installation → View Website

To setup your installation, enter the following information. [View Installation Video](#)

Administrative Information

Username *

Password *

Confirm *

Website Information

Website Name *

Template

Language

Congratulations! You have successfully deployed DNN Platform using Amazon Web Services. To verify that it works, in the web browser on your local computer, type the DNS address of the Amazon EC2

instance you recorded in [Step 4: Launch an Instance \(p. 10\)](#). Add `dotnetnuke` at the end of the address (e.g., `http://ec2-107-21-89-39.compute-1.amazonaws.com/dotnetnuke`).

In the future, if you decide you want to launch more instances and deploy your application on them, you won't have to customize each one. [Step 6: Create a Custom AMI \(p. 23\)](#) explains how to create a custom Amazon Machine Image (AMI) with all your configuration changes.

Step 6: Create a Custom AMI


Now that we have customized our Amazon EC2 instance, we can save this Amazon Machine Image (AMI) and launch future environments with this saved configuration.

To create an AMI from a running Amazon EC2 instance

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. Make sure that **US East (N. Virginia)** is selected in the region selector of the navigation bar.
3. In the navigation pane, click **Instances**.
4. On the **Instances** page, right-click your running instance, and then click **Create Image**.
5. In the **Create Image** dialog box, fill in a unique image name and an optional description of the image (up to 255 characters), and then click **Create Image**.

Amazon EC2 terminates the instance, takes images of any volumes that were attached, creates and registers the AMI, and then relaunches the instance.

6. The **Create Image** dialog shows the AMI ID. Make a note of it; you will need it in a later task.
7. To view the status of the new AMI, click **AMIs** in the navigation pane. While the new AMI is being created, its status is *pending*. It takes a few minutes for the whole process to finish.
8. When the status of your AMI changes to *available*, go to the **Snapshots** page by clicking **Snapshots** in the navigation pane. View the new snapshot that was created for the AMI. Any instance that you launch from the new AMI uses this snapshot as its root device volume.



Eventually, you'll probably want to have multiple Amazon EC2 instances running across multiple Availability Zones. If one Availability Zone becomes unavailable, the traffic will be rerouted to another Availability Zone. An Elastic Load Balancer will enhance the availability of your application, whether all of your instances are in the same Availability Zone or in multiple Availability Zones. To create an Elastic Load Balancer, move on to [Step 7: Create an Elastic Load Balancer \(p. 23\)](#).


Step 7: Create an Elastic Load Balancer

Elastic Load Balancing automatically distributes and balances the incoming application traffic among all the instances you are running, improving the availability and scalability of your application. The service also makes it easy to add new instances or remove underused instances when you need to increase or decrease the capacity of your application. The following diagram shows how the load balancer works. In this diagram, the load balancer contains two listeners. The first listener accepts traffic on port 80 using HTTP and forwards these requests to the Amazon EC2 instances using HTTP on port 8080. The other

Getting Started with AWS Computing Basics for Windows

Step 7: Create an Elastic Load Balancer

listener accepts traffic on port 443 using HTTPS and forwards these requests to the Amazon EC2 instances using HTTPS on port 4443.



You can specify the protocol and port for both the client and the Amazon EC2 instances. In this step, we will create a load balancer for an HTTP service. We'll specify that the load balancer listen on port 80 for incoming traffic from clients and then distribute traffic on port 80 to the instances.

As soon as your load balancer becomes available, you're billed for each hour or partial hour that you keep the load balancer running. For more information about Elastic Load Balancing pricing, see the [Elastic Load Balancing](#) details page.

For more information about elastic load balancers, go to the [Elastic Load Balancing Documentation](#).

To create a load balancer

1. Define a load balancer:
 - a. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
 - b. In the top navigation bar, click **US East (N. Virginia)** in the region selector.
 - c. In the left navigation pane, click **Load Balancers**.
 - d. Click **Create Load Balancer**.
 - e. In the **Create a New Load Balancer** wizard, on the **Define Load Balancer** page, enter a name for your load balancer. In this example, type **MyLB**.

Getting Started with AWS Computing Basics for Windows

Step 7: Create an Elastic Load Balancer

Create a New Load Balancer Cancel

DEFINE LOAD BALANCER CONFIGURE HEALTH CHECK ADD EC2 INSTANCES REVIEW

This wizard will walk you through setting up a new load balancer. Begin by giving your new load balancer a unique name so that you can identify it from other load balancers you might create. You will also need to configure ports and protocols for your load balancer. Traffic from your clients can be routed from any load balancer port to any port on your EC2 instances. By default, we've configured your load balancer with a standard web server on port 80.

Load Balancer Name:

Create LB inside:

Create an internal load balancer: (what's this?)

Listener Configuration:

Load Balancer Protocol	Load Balancer Port	Instance Protocol	Instance Port	Actions
HTTP	80	HTTP	80	<input type="button" value="Remove"/>
HTTP	<input type="text"/>	HTTP	<input type="text"/>	<input type="button" value="Save"/>

- f. Leave the **Listener Configuration** set to the default value for this example. The Load Balancer Port and Protocol specifies the port and protocol that the load balancer will use to listen for traffic from clients. The Instance Protocol and Port specifies the port and protocol the load balancer will use to route traffic to the instances. For example, if you want the load balancer to forward traffic to the instances using port 8080, you can specify that here.

Note

After you configure the listener information, you cannot change it. If you want to update this information, you will need to create a new load balancer.

- g. Click **Continue**.
2. Configure the health check:

Elastic Load Balancing routinely checks the health of each load-balanced Amazon EC2 instance. If Elastic Load Balancing finds an unhealthy instance, it stops sending traffic to the instance and reroutes traffic to healthy instances.

- a. On the **Configure Health Check** page under **Configuration Options**, do the following:
- Leave **Ping Protocol** set to its default value of **HTTP**. In the future, if you want to use a more secure protocol for the load balancer to send ping requests to your instances, you can use HTTPS and specify a different port. For information on using HTTPS with Elastic Load Balancing, see [Elastic Load Balancing Developer Guide](#) in *Elastic Load Balancing Developer Guide*.
 - Leave **Ping Port** set to its default value of 80.

Elastic Load Balancing uses the ping port to send health check queries to your Amazon EC2 instances.

Note

If you specify a ping port value, your Amazon EC2 instances must accept incoming traffic on the port that you specify. You can set a port value other than 80, and you can change this value at any time.

**Getting Started with AWS Computing Basics for
Windows
Step 7: Create an Elastic Load Balancer**

- In the **Ping Path** box, replace the default value with a single forward slash ("/").

Elastic Load Balancing sends health check queries to the ping path you specify. This example uses a single forward slash so that Elastic Load Balancing sends the query to your HTTP server's default home page, whether that default page is named `index.html`, `default.html`, or a different name. When you deploy your application, consider creating a special lightweight file that responds only to the health check. Doing so helps differentiate between traffic that is hitting your site and responses to the load balancer.

- b. Under **Advanced Options**, set the **Healthy Threshold** to **2**. Accept the default values on the other options.

Typically, the default value of 10 is fine for a healthy threshold. To expedite this tutorial, we specify 2 so you don't have to wait as long to see healthy instances.

The screenshot shows the 'Create a New Load Balancer' wizard in the AWS Management Console, specifically the 'Configure Health Check' step. The progress bar at the top indicates the current step is 'CONFIGURE HEALTH CHECK', with previous steps 'DEFINE LOAD BALANCER' and 'ADD EC2 INSTANCES' completed, and 'REVIEW' remaining. Below the progress bar, a text block explains that the load balancer will perform health checks on EC2 instances and route traffic only to those that pass. The 'Configuration Options' section includes a dropdown for 'Ping Protocol' set to 'HTTP', a text box for 'Ping Port' set to '80', and a text box for 'Ping Path' set to '/'. The 'Advanced Options' section features four sliders: 'Response Timeout' set to 5 seconds, 'Health Check Interval' set to 0.5 minutes, 'Unhealthy Threshold' set to 2, and 'Healthy Threshold' set to 2. To the right of these sliders, a legend explains each parameter: 'Response Timeout' is the time to wait for a response (2-60 sec), 'Health Check Interval' is the time between checks (0.1 min - 5 min), 'Unhealthy Threshold' is the number of consecutive failures before declaring an instance unhealthy, and 'Healthy Threshold' is the number of consecutive successes before declaring an instance healthy. At the bottom, there are '< Back' and 'Continue >' buttons.

- c. Click **Continue**.

3. On the **Add EC2 Instances** page, click **Continue**.

Getting Started with AWS Computing Basics for Windows

Step 7: Create an Elastic Load Balancer

Create a New Load Balancer
Cancel

DEFINE LOAD BALANCER
CONFIGURE HEALTH CHECK
ADD EC2 INSTANCES
REVIEW

The table below lists all your running EC2 Instances that are not already behind another load balancer or part of an auto-scaling capacity group. Check the boxes in the Select column to add those instances to this load balancer.

Manually Add Instances to Load Balancer:

Select	Instance	Name	State	Security Groups	Availability Zone
No records found.					

[select all](#) | [select none](#)

Availability Zone Distribution:
No instances selected

< Back
Continue

- Review your settings. To make changes to the settings, click the **Edit** link for a specific step in the process.

Create a New Load Balancer
Cancel

DEFINE LOAD BALANCER
CONFIGURE HEALTH CHECK
ADD EC2 INSTANCES
REVIEW

DEFINE LOAD BALANCER

Load Balancer Name: MyLB
Scheme: internet-facing
Port Configuration: 80 (HTTP) forwarding to 80 (HTTP)

[Edit Load Balancer Definition](#)

CONFIGURE HEALTH CHECK

Ping Target: HTTP:80:/
Timeout: 5
Interval: 0.5

Unhealthy Threshold: 2
Healthy Threshold: 2

[Edit Health Check](#)

ADD EC2 INSTANCES

EC2 Instances: No instances

[Edit EC2 Instance Selection](#)

VPC INFORMATION

VPC:
Subnets:

< Back

Create


Please review your selections on this page. Clicking "Create" will launch your load balancer. Check the Amazon EC2 product page for load balancer pricing info

Important

After you create a load balancer, you can modify any of the settings except for **Load Balancer Name** and **Port Configuration**. To rename a load balancer or change its port configuration, create a replacement load balancer.

**Getting Started with AWS Computing Basics for
Windows
Step 7: Create an Elastic Load Balancer**

5. Click **Create**.
6. On the **Confirmation** page, click **Close**.



Your new load balancer now appears in the list.

As a best practice, you should have sufficient instances across Availability Zones to survive the loss of any one Availability Zone. Therefore, we will ensure that our load balancer points to multiple Availability Zones in the next step.

7. Record the public DNS address:
 - a. In the **Load Balancers** pane, click **MyLB**.
 - b. Click the **Description** tab.



- c. Write down the public DNS address. You will need it later in this tutorial.

8. Add an Availability Zone:

Getting Started with AWS Computing Basics for Windows Where You're At

- In the list of load balancers, click **MyLB**.
- Click the **Instances** tab.
- Click the plus icon.

The screenshot shows the AWS Management Console interface for a load balancer named 'MyLB'. At the top, there are buttons for 'Create Load Balancer' and 'Delete'. Below that, there's a search bar and navigation controls. The main content area shows a table of load balancers with columns for 'Load Balancer Name', 'DNS Name', 'Port Configuration', and 'Availability Zones'. The selected load balancer 'aztest-ElasticLoad-' is shown with its DNS name and port configuration. Below this, there's a section for '1 Load Balancer selected' and a tabbed interface with 'Instances', 'Health Check', 'Security', and 'Listeners'. The 'Instances' tab is active, showing a table with columns for 'Instance', 'Name', 'Availability Zone', 'Status', and 'Actions'. Below the instances table, there's a section for 'Availability Zones' with columns for 'Availability Zone', 'Instance Count', 'Healthy?', and 'Actions'. The 'us-east-1c' zone is listed with 0 instances and a 'No (why?)' status. A red circle highlights the plus icon in the 'Actions' column for 'us-east-1c'.

- In the **Add and Remove Availability Zones** dialog box do the following:
 - Click **us-east-1b: 0 instances**.
 - Click **us-east-1c: 0 instances**.
 - Click **Save**.

The screenshot shows the 'Add and Remove Availability Zones' dialog box. It has a title bar with 'Add and Remove Availability Zones' and a 'Cancel' button. The main text reads: 'Load balancers distribute requests evenly among the availability zones to which they are assigned. Add or remove zones from the Load Balancer below.' Below this, there's a list of availability zones with checkboxes: 'us-east-1a: 0 instances', 'us-east-1b: 0 instances', 'us-east-1c: 0 instances', 'us-east-1d: 0 instances', and 'us-east-1e: 0 instances'. The checkboxes for 'us-east-1b' and 'us-east-1c' are checked. Below the list, there's a warning icon and text: 'You are enabling an Availability Zone that is empty (has no running instances)'. At the bottom, there's a 'Save' button.

In a later task, you will launch instances in these two Availability Zones by using Auto Scaling. You'll see that the Availability Zones column for the load balancer is updated for both Availability Zones.

Where You're At

Here's where you are in building your architecture.



In [Step 4: Launch an Instance](#) (p. 10), you set a security group to allow all traffic to connect to your Amazon EC2 instance via port 80 (HTTP). Now that you have created an Elastic Load Balancer, you can update your security group to allow only incoming HTTP traffic from your Elastic Load Balancer. Move on [Step 8: Update Your Amazon EC2 Security Group](#) (p. 30).

Step 8: Update Your Amazon EC2 Security Group

In [Step 4: Launch an Instance](#) (p. 10), we created a security group that enabled HTTP over port 80. The security group allows all traffic to access the Amazon EC2 instance directly over HTTP/80. Since you created an Elastic Load Balancer, a more secure method is to allow only the load balancer to access your Amazon EC2 instance. In this task, you will update your security group to allow only the load balancer to access your Amazon EC2 instance over HTTP/80.

To configure your security group

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. In the top navigation bar, click **US East (N. Virginia)** in the region selector.
3. In the left navigation pane, click **Load Balancers**.
4. Select the load balancer that you created earlier, and click the **Security** tab. In the **Source Security Group** field, copy or write down the name of the security group that's associated with the load balancer. You will need the name to update your instance's security group rules.
5. In the left navigation pane, click **Security Groups**.
6. On the **Security Groups** page, click the security group `webappsecuritygroup` that you created in the previous procedure. If you cannot see your security group, you may need to select **All Security Groups** from the filter list.
7. Click the **Inbound** tab, and click **Edit**.
8. In the row that displays port 80 (HTTP), select **Custom IP** from the **Source** field, and enter the name of the security group that's associated with your load balancer, for example, `amazon-elb/amazon-elb-sg`.

Type	Protocol	Port Range	Source
RDP	TCP	3389	Anywhere 0.0.0.0/0
MS SQL	TCP	1433	Anywhere 0.0.0.0/0
HTTP	TCP	80	Custom IP amazon-elb/amazon-

9. Click **Save**. The rules for this security group will be enforced when the instances that use these rules are launched.

Now that you have configured your Amazon EC2 security group, you can move on to [Step 9: Launch Amazon EC2 Instances Using Auto Scaling \(p. 31\)](#). [Auto Scaling](#) can adjust the number of running instances as traffic levels change.

Step 9: Launch Amazon EC2 Instances Using Auto Scaling

Auto Scaling launches and terminates Amazon EC2 instances automatically according to user-defined policies, schedules, and alarms. You can use Auto Scaling to maintain a fleet of Amazon EC2 instances that can adjust to any presented load. You can also use Auto Scaling to bring up multiple instances in a group at one time.

As the name implies, Auto Scaling responds automatically to changing conditions. All you need to do is specify how it should respond to those changes. For example, you can instruct Auto Scaling to launch an additional instance whenever CPU usage on one or more existing instances exceeds 60 percent for ten minutes, or you could tell Auto Scaling to terminate half of your website's instances over the weekend, when you expect traffic to be low.

Auto Scaling can ensure that the instances in your fleet are performing optimally so that your applications continue to run efficiently. Auto Scaling groups can even work across multiple Availability Zones, so that if an Availability Zone becomes unavailable, Auto Scaling will automatically redistribute traffic to applications in a different Availability Zone. With Auto Scaling, you can ensure that you always have at least one healthy instance running. For more information, see [Auto Scaling](#).

In this example, you will set up the basic infrastructure that must be in place to get Auto Scaling started for most applications. You'll do the following:

- Create a launch configuration.
- Create an Auto Scaling group.
- Create a policy for your Auto Scaling group.

For the purposes of this tutorial, we'll set up an Amazon EC2 application to be load-balanced and auto-scaled with a minimum number of two instances and maximum number of two instances. By setting the minimum and maximum number to be the same, you can ensure that you always have the desired number of instances even if one instance fails. When you create your actual website, as a best practice you should launch sufficient instances across Availability Zones to survive the loss of any one Availability Zone. Additionally, the maximum number of instances must be greater than the minimum to make use of the Auto Scaling feature.

You can control how big your fleet gets by specifying a maximum number of instances. In this example, Auto Scaling is configured to add one instance when there is a increase in load. We will define the policy in this topic, and in the next section we will create a CloudWatch alarm to take action on the policy when the average NetworkOut exceeds a threshold of 6,000,000 bytes for 5 minutes. Auto Scaling and Amazon CloudWatch work together to launch or terminate instances according to the policies you create. To save time, we will create just one policy; however, you can create more policies, such as a policy to terminate instances when load decreases.

If you haven't already installed the Auto Scaling command line tools, you need to do that now. To install the Auto Scaling command line tools to your local computer go to [Auto Scaling Command Line Tool](#). For instructions on configuring your Auto Scaling tools, go to [Install the Command Interface](#) in the *Auto Scaling Developer Guide*.

**Getting Started with AWS Computing Basics for
Windows**
**Step 9: Launch Amazon EC2 Instances Using Auto
Scaling**

To set up an auto-scaled, load-balanced Amazon EC2 application

1. Open a command prompt window: From a local Windows computer, click **Start**. In the **Search** box, type `cmd` and then press Enter.
2. The launch configuration is a template for the instances you launch in your Auto Scaling group. To define the launch configuration for this example, we will use the `as-create-launch-config` command. The following parameters define your launch configuration.
 - *image-id* is the AMI ID. Use the custom AMI ID that you created in [Step 6: Create a Custom AMI \(p. 23\)](#).
 - *instance-type* contains basic information, such as operating system, memory, and local storage, about the instance that you will launch. For this example, use the same instance type that you used when you first launched your instance.
 - *key* is the key pair used to connect to your instances. Use the same key pair that you created when you first launched your instance.
 - *group* is the security group where you defined the access rules for your instance. Use the same security group that you created when you first launched your instance.

Note

If you launched your instance and created your security group in a VPC, you will need to specify the security group's ID in the command, and not its name.

- *monitoring-disabled* specifies that you want to use basic monitoring instead of detailed monitoring. By default, detailed monitoring is enabled. For more information about basic and detailed monitoring, go to [Amazon CloudWatch](#).

We will not specify a region, because we want to use the default region, US East (N. Virginia). At the command prompt, type the following, and then press Enter:

```
PROMPT>as-create-launch-config MyLC --image-id ami-191dc970 --instance-type  
m1.large --group webappsecuritygroup --key mykeypair --monitoring-disabled
```

Auto Scaling returns the following:

```
OK-Created launch config
```

Note

You can copy the commands from this document and paste them in the Command Prompt window. To paste the contents in the command line window, right-click in the Command Prompt window, and then click Paste. If you have trouble getting the commands to work, ensure that the command was entered correctly.

You have now created your launch configuration.



3. To create an Auto Scaling group in which you can launch multiple Amazon EC2 instances, you will use the `as-create-auto-scaling-group` command. Use the following parameters to define your Auto Scaling group.
 - *launch-configuration* is the name of the launch configuration that you created in the previous step.

**Getting Started with AWS Computing Basics for
Windows**
**Step 9: Launch Amazon EC2 Instances Using Auto
Scaling**

- *availability-zones* specifies the Availability Zones where the Amazon EC2 instances in the Auto Scaling group will be launched. In this example, you will specify two Availability Zones.

Specifying multiple Availability Zones is a good practice for building fault-tolerant applications. If one Availability Zone experiences an outage, traffic will be routed to another Availability Zone. The number of instances that are launched in the Auto Scaling group will be evenly distributed across the Availability Zones.

- *min-size* and *max-size* set the minimum and maximum number of Amazon EC2 instances in the Auto Scaling group. By setting the minimum and maximum number to be the same, you can fix the number of instances in your group. In this example, set both the minimum and maximum number to 2.
- *load-balancer* is the name of the load balancer that is used to route traffic to the Auto Scaling group.

At the command prompt, type the following, and then press Enter.

```
PROMPT>as-create-auto-scaling-group MyAutoScalingGroup --launch-configuration  
MyLC --availability-zones us-east-1b, us-east-1c --min-size 2 --max-size  
2 --load-balancers MyLB
```

Note

If you do not have permission to launch instances in us-east-1b, then try us-east-1d.

Auto Scaling returns output similar to the following example:

```
OK-Created AutoScalingGroup
```

4. To create a policy to enlarge your fleet of instances, we will use the `as-put-scaling-policy` command. This policy applies to the Auto Scaling group you created in the previous step. Use the following parameters when defining your Auto Scaling policy.
 - *auto-scaling-group* is the name of the Auto Scaling group that you want to apply the policy to. Use the Auto Scaling group name that you created in the previous step.
 - *adjustment* is the number of instances you want to increment or decrement. For this example, use 1.
 - *type* is the type of policy you want to create. For this example, use `ChangeInCapacity` to change the fleet size of your instances.
 - *cooldown* is the time, in seconds, after an action before Auto Scaling should evaluate conditions again.

At the command prompt, type the following, and then press Enter:

```
PROMPT>as-put-scaling-policy MyScaleUpPolicy --auto-scaling-group MyAutoScal  
ingGroup --adjustment=1 --type ChangeInCapacity --cooldown 300
```

Auto Scaling returns output similar to the following example:

```
POLICY-ARN arn:aws:autoscaling:us-east-1:012345678901:scalingPolicy:cbe7da4e-  
5d00-4882-900a-2f8113431e30:autoScalingGroupName/MyAutoScalingGroup:policy  
Name/MyScaleUpPolicy
```

Note

To save time, we created only a policy to add an instance. In most cases, you would also create a policy to terminate one or more instances when traffic declines. Auto Scaling can decrease the number of instances when your application doesn't need the resources, saving you money. To create a policy for terminating an instance, start from the policy you just created, change the policy name, and then change the value of adjustment from 1 to -1. You use "--adjustment=-1" on a Windows machine.

At the command prompt, type the following, and then press Enter:

```
PROMPT>as-put-scaling-policy MyScaleDownPolicy --auto-scaling-group  
MyAutoScalingGroup "--adjustment=-1" --type ChangeInCapacity --cooldown  
300
```

5. To verify that your Auto Scaling group exists, we'll use the `as-describe-auto-scaling-groups` command. At the command prompt, type the following, and then press Enter:

```
PROMPT>as-describe-auto-scaling-groups MyAutoScalingGroup --headers
```

Auto Scaling returns the following:

```
AUTO-SCALING-GROUP  GROUP-NAME          LAUNCH-CONFIG  AVAILABILITY-ZONES  
  MIN-SIZE  MAX-SIZE  DESIRED-CAPACITY  
AUTO-SCALING-GROUP  MyAutoScalingGroup  MyLC           us-east-1b,us-east-  
1c  2          2          2  
INSTANCE  INSTANCE-ID  AVAILABILITY-ZONE  STATE      STATUS  LAUNCH-CONFIG  
INSTANCE  i-xxxxxxx    us-east-1b        InService  Healthy  MyLC  
INSTANCE  i-xxxxxxx    us-east-1c        InService  Healthy  MyLC
```

Your Amazon EC2 application has been launched as an auto-scaled and load-balanced application.


For more information about Auto Scaling, see the [Auto Scaling Documentation](#).

Caution

You will continue to incur costs as long as your Amazon EC2 instances are running. If at any time you want to terminate these instances, see [Terminate Your Amazon EC2 Instances in Your Auto Scaling Group](#) (p. 43).

Where You're At

Here's where you are in building your architecture.



Now that you have created your Auto Scaling group and your Amazon EC2 instance is up and running, you'll want a way to monitor the health of your instance. In the next step, you'll create an Amazon CloudWatch alarm to track the Auto Scaling policy you just created.

Step 10: Create a CloudWatch Alarm

Amazon CloudWatch is a web service that enables you to monitor, manage, and publish various metrics and to configure alarm actions based on those metrics.

With Amazon CloudWatch, you can collect, analyze, and view system and application metrics so that you can make operational and business decisions quickly and confidently. Amazon CloudWatch automatically collects metrics about your AWS resources, such as the performance of your Amazon EC2 instances. You can publish your own metrics directly to Amazon CloudWatch.

You can use Amazon CloudWatch to diagnose problems by looking at system performance before and after a problem occurs. Amazon CloudWatch helps you identify the cause and verify your fix by tracking performance in real time. For example, you can set up Amazon CloudWatch to send you email right away when your application slows down, so you can go back and discover, for example, that a particular database was being overloaded. When you have fixed the problem, you can use Amazon CloudWatch to watch response times return to normal. For more information about creating CloudWatch alarms, go to [Creating CloudWatch Alarms](#) in the Amazon CloudWatch Developer Guide.

A common use for Amazon CloudWatch is to keep your applications and services healthy and running efficiently. For example, you can use it to discover that your website runs best when network traffic to your Amazon EC2 instances remains below a certain threshold. You can then create an Auto Scaling policy to ensure that you always have the right number of instances to match the amount of traffic you have.

In the previous task, we created an Auto Scaling policy to add to the number of running instances. In this task, we'll associate that policy with an alarm action. When the alarm is triggered, Auto Scaling is notified and makes the appropriate changes to your resources.

You'll create an alarm with the following characteristics:

Getting Started with AWS Computing Basics for Windows
Step 10: Create a CloudWatch Alarm

MyNetworkOutAlarm

Description: NetworkOut at 6,000,000 bytes for >= 5 minutes

Namespace: AWS/EC2


Statistic: Average

Metric: NetworkOut

MCT: >=6,000,000

CloudWatch Alarm

The following diagram demonstrates how Amazon CloudWatch and Auto Scaling work together. The Amazon EC2 instance reports its NetworkOut metric to Amazon CloudWatch. Amazon CloudWatch fires an alarm if the specified threshold has been exceeded and reports this to the Auto Scaling Group. The Auto Scaling group then takes action based on the policy that is set.



This topic walks you through creating a CloudWatch alarm to alert the application when the threshold is exceeded. To save time, we'll create just one alarm; however, you can apply the same procedure to create other alarms. For example, you could create another alarm to notify Auto Scaling that it needs to terminate an instance. For more information about Amazon CloudWatch, see the [Amazon CloudWatch details page](#).

To create an Amazon CloudWatch alarm

1. Select a metric for your alarm:
 - a. Open the Amazon CloudWatch console at <https://console.aws.amazon.com/cloudwatch/>.
 - b. In the top navigation bar, click **US East (N. Virginia)** in the region selector.

**Getting Started with AWS Computing Basics for
Windows
Step 10: Create a CloudWatch Alarm**

- c. In the left navigation pane, click **Alarm**.
- d. In the details pane, click **Create Alarm**.
- e. In the **Create Alarm Wizard**, on the **Select Metric** page, in the **Viewing** list, select **EC2: Aggregated by Auto Scaling Group**.

Create Alarm Wizard Cancel X

SELECT METRIC DEFINE ALARM CONFIGURE ACTIONS REVIEW

Set an alarm for any of your CloudWatch metrics. Your alarm will react automatically when a metric reaches your specified threshold. Available actions include sending Amazon SNS notifications and executing Auto Scaling policies. To get started, select a metric. Then preview it, select a statistic and sampling period, and click **Continue**.

Statistic: Average
Period: 5 Minutes

Important: select a sample period. A shorter period allows a more sensitive alarm. A longer period smooths out brief spikes.

NetworkOut (Bytes)

120,000
100,000
80,000
60,000
40,000

1/13 14:00 1/13 16:00 1/13 18:00

Viewing: EC2: Aggregated by Auto Scaling Group MyAutoScalingGroup Search 1 to 42 of 42 Metrics

MyAutoScalingGroup	CPUUtilization
MyAutoScalingGroup	DiskReadBytes
MyAutoScalingGroup	DiskReadOps
MyAutoScalingGroup	DiskWriteBytes
MyAutoScalingGroup	DiskWriteOps
MyAutoScalingGroup	NetworkIn
MyAutoScalingGroup	NetworkOut
MyAutoScalingGroupLinux	CPUUtilization
MyAutoScalingGroupLinux	DiskReadBytes
MyAutoScalingGroupLinux	DiskReadOps
MyAutoScalingGroupLinux	DiskWriteBytes
MyAutoScalingGroupLinux	DiskWriteOps

Continue

- f. Click the **MyAutoScalingGroup/NetworkOut** row, and then click **Continue**.

Note

It can take up to 15 minutes for the Auto Scaling group to appear in the list. If you do not see your Auto Scaling group, wait up to 15 minutes, and then try again.

2. Define the alarm:

On the **Define Alarm** page of the **Create Alarm** wizard, do the following, and then click **Continue**:

- In the **Name** box, type **MyNetworkOutAlarm**.
- In the **Description** box, type a description.
- In the **Define Alarm Threshold** section, click **>=**, type **6000000** in the first box and **5** in the minutes box. For your own application, you can do some load testing to see what values make the most sense.

Getting Started with AWS Computing Basics for Windows

Step 10: Create a CloudWatch Alarm

Create Alarm Wizard

SELECT METRIC **DEFINE ALARM** CONFIGURE ACTIONS REVIEW

Provide the details and threshold for your alarm. Use the graph below to help set the appropriate threshold. Average

Identify Your Alarm

Assign your alarm a name and description.

Name:

Description:

Define Alarm Threshold

Alarms have three states: ALARM, OK, and INSUFFICIENT DATA. The state of your alarm changes according to a threshold you specify. First, define the criterion for entering the ALARM state. Later, you can specify an action to be taken when your alarm enters any of the three states.

This alarm will enter the ALARM state when NetworkOut is \geq for minutes.

Metric: NetworkOut
Period: 5 Minutes
Statistic: Average

< Back **Continue** >

3. Define your actions:

- a. On the **Configure Actions** page of the **Create Alarm** wizard, do the following, and then click **Add Action**.
 - Under **When Alarm state is**, click **ALARM**.
 - Under the **Take Action** list, click **Auto Scaling Policy**.
 - In the **Auto Scaling Group** list, click **MyAutoScalingGroup**.
 - In the **Policy** list, click **MyScaleUpPolicy (Add 1 instance)**.
- b. Do the following, and then click **Continue**.
 - In the new row that is created, under **When Alarm state is**, click **ALARM**.
 - Under the **Take Action** list, click **Send Notification**.
 - In the **Topic** box, click **Create New Email Topic** and then type a topic name.
 - In the **Email(s)** box, type an email address where notifications will be sent.

Getting Started with AWS Computing Basics for Windows
Step 10: Create a CloudWatch Alarm

The screenshot shows the 'Create Alarm Wizard' window with the 'CONFIGURE ACTIONS' step selected. The progress bar at the top indicates the current step. Below the progress bar, there is a heading 'Define Your Actions' and a table for configuring actions.

Define what actions are taken when your 'MyNetworkOutAlarm' alarm changes.

You can define multiple actions for a single alarm. For example, you may want to scale out your fleet and send an email to your page when this alarm enters the ALARM state, and then send another all-clear email when it returns to the OK state.

Define Your Actions

Actions define what steps you want to automate when the alarm state changes. For example, you can send a message using email via the Simple Notification Service (SNS). You can also execute an Auto Scaling Policy, if you have one configured ([learn about policies](#)).

When Alarm state is	Take action	Action details	
ALARM	Auto Scaling Policy	Auto Scaling Group: MyAutoScalingGroup Policy: MyScaleUpPolicy (Add 1)	REMOVE
ALARM	Send Notification	Topic: MyNetworkOutAlarm Email(s): <small>A topic is a communication channel that can be reused across Send Notification actions. Please enter a new topic name and a list of comma-separated email addresses.</small>	ADD ACTION

< Back Continue >

4. On the **Review** page, review the settings. If everything is all right, click **Create Alarm**.

The screenshot shows the 'Create Alarm Wizard' window with the 'REVIEW' step selected. The progress bar at the top indicates the current step. Below the progress bar, there is a heading 'Alarm Definition' and sections for 'Metric' and 'Alarm Actions'.

If you want to make any changes to this alarm, click **Back** or select a step on the right to edit.

Alarm Definition Edit Definition

Name: MyNetworkOutAlarm
Description: This is my network out alarm.
In ALARM state when: the value is ≥ 6000000 for 5 minutes

Metric Edit Metric

Namespace: AWS/EC2
MetricName: NetworkOut
AutoScalingGroupName: MyAutoScalingGroup
Period / Statistic: 5 Minutes / Average

Alarm Actions Edit Actions

Actions:

When alarm state is "ALARM "

Action Type: Auto Scaling Policy

Action: Use policy MyScaleUpPolicy (Add 1 instance) for group MyAutoScalingGroup

When alarm state is "ALARM "


Action Type: Send Notification to New Topic

Action: Notify topic: MyNetworkOutAlarm (janedoe@example.com)


< Back Create Alarm >

5. On the confirmation page, click **Close**.

Getting Started with AWS Computing Basics for Windows Where You're At




On the dashboard page of the Amazon CloudWatch console, your new alarm now appears in the list.



If you create a MyScaleDownPolicy, you can create another alarm using the same steps.

Where You're At


Here's where you are in building your architecture.



Getting Started with AWS Computing Basics for Windows Where You're At

Congratulations! You have successfully deployed your web application to EC2 using the some of the essential building blocks of AWS. To verify that everything is working as it should, do the following:

1. Refresh your browser. You should no longer be able to access your website, because you updated your security group to allow access only through your Elastic Load Balancer.
2. Type the public DNS address of your Elastic Load Balancer which you recorded in [Step 7: Create an Elastic Load Balancer \(p. 23\)](#), to verify that you can see your application. Remember to append `/dotnetnuke/` to the DNS address.



Note

Because we deployed SQL Express on each Amazon EC2 instance, each instance is running its own local copy of the database. When you view your website, you may see different content. There are several ways you could change this architecture to keep your data in sync across instances, including using [Amazon Relational Database Service \(Amazon RDS\)](#). For more information about deploying your web application using Amazon RDS, go to [Step 10: Add Amazon RDS](#) in *Getting Started with AWS Web Application Hosting for Microsoft Windows*.

In this tutorial, you learned how to deploy your web application by using the following AWS products:

- Amazon EC2 to run your application
- Elastic Load Balancing to load balance traffic across your running instances
- Auto Scaling to automatically add and terminate instances according to policies that you set
- Amazon CloudWatch to monitor your instances and to notify you when thresholds you specify are exceeded

When you have a better understanding of the AWS services and how you want to use them, there is an easier way you can deploy your application. [AWS CloudFormation](#) helps you deploy resources in AWS without worrying about the order in which AWS services need to be provisioned or the subtleties of how

to make those dependencies work. To learn how to build sample template using the services we used in this tutorial, go to [Auto Scaling Group with LoadBalancer](#), [Auto Scaling Policies](#), and [CloudWatch Alarms](#) in the *AWS CloudFormation User Guide*.

If you are finished using your AWS resources, you can terminate them so that you are no longer billed. Move on to [Step 11: Clean Up](#) (p. 42).

Step 11: Clean Up

Topics

- [Delete Your CloudWatch Alarm](#) (p. 42)
- [Delete Your Elastic Load Balancer](#) (p. 43)
- [Terminate Your Amazon EC2 Instances in Your Auto Scaling Group](#) (p. 43)
- [Terminate Your Instance](#) (p. 45)
- [Delete a Key Pair](#) (p. 45)
- [Delete an Amazon EC2 Security Group](#) (p. 46)


Congratulations! You have just deployed your web application. To prevent accruing any further charges, terminate your environments and clean up your resources.

Delete Your CloudWatch Alarm


After you've decided that you no longer need the alarm, you can delete it.

To delete your alarm

1. Open the Amazon CloudWatch console at <https://console.aws.amazon.com/cloudwatch/>.
2. In the top navigation bar, click **US East (N. Virginia)** in the region selector.
3. In the left navigation pane, click **Alarms**.
4. Select the check box next to the alarm that you want to delete, and then click **Delete**.



5. When a confirmation message appears, click **Yes, Delete**.



Delete Your Elastic Load Balancer


As soon as your load balancer becomes available, AWS bills you for each hour or partial hour that you keep the load balancer running. After you've decided that you no longer need the load balancer, you can delete it.

To delete your load balancer

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. In the top navigation bar, click **US East (N. Virginia)** in the region selector.
3. In the left navigation pane, click **Load Balancers**.
4. Select the check box next to the load balancer you want to delete and then click **Delete**.



5. When a confirmation message appears, click **Yes, Delete**.



Elastic Load Balancing deletes the load balancer. As soon as the load balancer is deleted, you stop incurring charges for that load balancer.

Caution

Even after you delete a load balancer, the Amazon EC2 instances associated with the load balancer continue to run. You will continue to incur charges on the Amazon EC2 instances while they are running.

Terminate Your Amazon EC2 Instances in Your Auto Scaling Group

In this section you will first remove the Amazon EC2 instance, then delete the Auto Scaling group, and finally delete the launch configuration.

Getting Started with AWS Computing Basics for Windows

Terminate Your Amazon EC2 Instances in Your Auto Scaling Group

You must terminate all Amazon EC2 instances in an Auto Scaling group before you can delete the group. A simple way to terminate all instances in a group is to update the group so that both the minimum size and maximum size are set to zero.

To remove the Amazon EC2 instance from the Auto Scaling group

1. Open a command prompt window: From a Windows computer, click **Start**. In the Search box, type `cmd`, and then press **Enter**.
2. You'll use the `as-update-auto-scaling-group` command to update the Auto Scaling group that we created earlier. At the command prompt, type the following, and then press **Enter**:

```
PROMPT>as-update-auto-scaling-group MyAutoScalingGroup --min-size 0 --max-size 0
```

Auto Scaling returns the following:

```
OK-Updated AutoScalingGroup
```

3. Now you'll use the `as-describe-auto-scaling-groups` command to verify that Auto Scaling has removed the instance from `MyAutoScalingGroup`.

It can take a few minutes for the instance to terminate, so you might have to check the status more than once. At the command prompt, type the following, and then press **Enter**:

```
PROMPT>as-describe-auto-scaling-groups MyAutoScalingGroup --headers
```

If the instance termination is still in progress, Auto Scaling returns information similar to the following. (Your value for `INSTANCE-ID` will differ):

```
AUTO-SCALING-GROUP  GROUP-NAME          LAUNCH-CONFIG  AVAILABILITY-ZONES
LOAD-BALANCERS     MIN-SIZE  MAX-SIZE  DESIRED-CAPACITY
AUTO-SCALING-GROUP  MyAutoScalingGroup  MyLC          us-east-1b,us-east-
1c  MyLB          0          0          0
INSTANCE  INSTANCE-ID  AVAILABILITY-ZONE  STATE      STATUS  LAUNCH-CONFIG
INSTANCE  i-xxxxxxx    us-east-1c        InService  Healthy  MyLC
```

Note

You can also click **Instances** in the Amazon EC2 console to view the status of your instances.

When no instances exist in `MyAutoScalingGroup`, you can delete the group.

To delete the Auto Scaling group

- At the command prompt, type the following, and then press **Enter**:

```
PROMPT>as-delete-auto-scaling-group MyAutoScalingGroup
```

To confirm the deletion, type `y`, and then press **Enter**.

```
Are you sure you want to delete this MyAutoScalingGroup? [Ny]
```

Auto Scaling returns the following:

```
OK-Deleted MyAutoScalingGroup
```

All that remains now is to delete the launch configuration you created for this Auto Scaling group.

To delete the launch configuration

- At the command prompt, type the following, and then press **Enter**:

```
PROMPT>as-delete-launch-config MyLC
```

To confirm the deletion, type `y` and then press **Enter**.

```
Are you sure you want to delete this launch configuration? [Ny]
```

Auto Scaling returns the following:

```
OK-Deleted launch configuration
```

Terminate Your Instance

As soon as your instance starts to boot, AWS bills you for each hour or partial hour that you keep the instance running, even if the instance is idle. You can terminate the instance so you are no longer charged for it. Because this instance is not part of your Auto Scaling group, you'll need to terminate it manually.

To terminate an instance

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. In the top navigation bar, click **US East (N. Virginia)** in the region selector.
3. In the left navigation pane, click **Instances**.
4. Right-click the instance, and then click **Terminate**.
5. When you are prompted for confirmation, click **Yes, Terminate**. As soon as the instance status changes to **shutting down** or **terminated**, you stop incurring charges for that instance.

Delete a Key Pair

This is an optional step. You are not charged for keeping a key pair, and you may want to reuse the key pair for later use.

To delete a key pair

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. In the top navigation bar, click **US East (N. Virginia)** in the region selector.
3. In the left navigation pane, click **Key Pairs**.
4. Select the check box beside the key pair you want to delete, and then click **Delete**.
5. When a confirmation message appears, click **Yes**.

Delete an Amazon EC2 Security Group

To delete a security group

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. In the top navigation bar, click **US East (N. Virginia)** in the region selector.
3. In the left navigation pane, click **Security Groups**.
4. In the details pane, under **Security Groups**, select a security group you want to delete, and then click **Delete**.
5. Click **Yes, Delete**.

Pricing

Topics

- [Amazon EC2 Cost Breakdown \(p. 47\)](#)
- [Summing It All Up \(p. 50\)](#)
- [How to Further Save Costs \(p. 51\)](#)

The [AWS Simple Monthly Calculator](#) estimates your monthly bill. It provides a per-service cost breakdown, as well as an aggregate monthly estimate. You can also use the calculator to see an estimate and breakdown of costs for common solutions. This topic walks you through an example of using the AWS Simple Monthly Calculator to estimate your monthly bill.

Note

AWS pricing you see in this documentation is current at the time of publication. For the latest pricing information, go to [AWS Service Pricing Overview](#). For more information on how AWS pricing works, go to [How AWS Pricing Works](#).

Amazon EC2 Cost Breakdown

The following table shows the characteristics for Amazon EC2 we have identified for this web application architecture. In this example, we'll assume that you've moved into full production and you need between three and six instances: three instances run all the time, two additional instances are required to handle peak traffic, and another instance handles nightly backups.

Characteristic	Metric	Description
Clock Hours of Server Time	3 instances running 24 hours/day 2 instances running 8 hours/day 1 instances running 3 hours/day	Assuming an average of 30.5 days in a month, the full-time instances run 732 hours/month, the peak traffic instances run 244 hours/month, and the backup instances run 91.5 hours/month

**Getting Started with AWS Computing Basics for
Windows
Amazon EC2 Cost Breakdown**

Characteristic	Metric	Description
Machine Characteristics	1 ti.micro instance 5 m1.small instances	Micro - 613 MB of memory, up to 2 EC2 Compute Units (for short periodic bursts), Elastic Block Store (EBS) storage only, 32-bit or 64-bit platform Small- 1.7 GB of memory, 1 EC2 Compute Unit (1 virtual core with 1 EC2 Compute Unit), 160 GB of local instance storage, 32-bit platform For a list of instance types, go to http://aws.amazon.com/ec2/instance-types/ .
Additional Storage	1 EBS Volume Storage: 30 GB/Month 100 IOPS	The AMI is EBS-backed. The volume will have 30 GB provisioned storage, and 100 I/O requests per second made to the volume.
Data Transfer	Data In: 0.005 GB/day Data Out: 0.05 GB/day	There are approximately 1,000 hits per day. Each response is about 50 KB, and each request is about 5 KB.
Instance Scale	Between 3 and 6 instances	You need 3 instances running all the time, another two to handle peak traffic, and another to handle nightly backups.
Elastic Load Balancing	Hourly usage: 732 hrs/month Data processed: 1.525 GB/month	Elastic Load Balancing is used 24 hrs/day, 7 days/week Elastic Load Balancing processes a total of 0.055 GB/day (data in + data out)

The following image from the AWS Simple Monthly Calculator shows the cost breakdown for Amazon EC2.

Getting Started with AWS Computing Basics for Windows Amazon EC2 Cost Breakdown

Choose region: US-East / US Standard (Northern Virginia) Inbound Data Transfer is Free and Outbound Data Transfer is 1 GB free per region per month

Amazon Elastic Compute Cloud (Amazon EC2) is a web service that provides resizable compute capacity in the cloud. It is designed to make web-scale computing easier for developers. Amazon Elastic Block Store (EBS) provides persistent storage to Amazon EC2 instances. [Clear Form](#)

Compute: Amazon EC2 On-Demand Instances:

Description	Instances	Usage	Instance Type	Operating System	Tenancy	Detailed Monitoring
	1	3 Hours/Day	Micro <input type="checkbox"/> EBS-Optimized	Windows	Default	<input type="checkbox"/>
	3	24 Hours/Day	Small <input type="checkbox"/> EBS-Optimized	Windows	Default	<input type="checkbox"/>
	2	8 Hours/Day	Small <input type="checkbox"/> EBS-Optimized	Windows	Default	<input type="checkbox"/>

Compute: Amazon EC2 Reserved Instances:

Description	Instances	Usage	Instance Type	Operating System	Offering and Term	Tenancy	Detailed Monitoring
	0	0 Hours/Month	Small <input type="checkbox"/> EBS-Optimized	Linux	Medium Utilization 3 yr term	Default	<input type="checkbox"/>

Storage: Amazon EBS Volumes:

Description	Volumes	Volume Type	Storage	IOPS	Snapshot Storage
	6	Standard	30 GB	100	0 GB-month of Storage

Elastic IP:

Number of Additional Elastic IPs:

Elastic IP Non-attached Time: Hours/Month

Number of Elastic IP Remaps: Per Month

Data Transfer:

Inter-Region Data Transfer Out: GB/Day

Data Transfer Out: GB/Day

Data Transfer In: GB/Month

Intra-Region Data Transfer: GB/Month

Public IP/Elastic IP Data Transfer: GB/Month

Elastic Load Balancing:

Number of Elastic LBs:

Total Data Processed by all ELBs: GB/Day

The total monthly cost is the sum of the cost of the running instances, Amazon Elastic Block Store volumes and I/O requests, Elastic Load Balancer, and the data processed by the Elastic Load Balancers. Because we used basic monitoring and only one metric and alarm for our Amazon EC2 instances, there is no additional charge for Amazon CloudWatch monitoring.

Variable	Formula	Calculation
Instance Cost	Instance cost per hour	\$0.115
	Number of instances	3
	x Clock hours of server time	x 732
	-----	-----
		\$252.54
Instance Cost	Instance cost per hour	\$0.115
	Number of instances	2
	x Clock hours of server time	x 244
	-----	-----
		\$56.12

**Getting Started with AWS Computing Basics for
Windows
Summing It All Up**

Variable	Formula	Calculation
Instance Cost	Instance cost per hour Number of instances x Clock hours of server time -----	\$0.02 1 x 91.5 ----- \$1.83
Additional Storage	Storage rate x Storage Amount (GB) + (I/O requests rate x seconds per month x Request rate(per 1M requests)) x Number of Volumes -----	\$0.10 X 30 + (100 x ~2.6M x \$0.10)/1M x 6 ----- \$176.11
Elastic Load Balancing	Hours used x Hourly rate + (Data processed (GB) x Process rate) -----	732 x \$0.025 + 1.6775 x \$0.008 ----- \$18.31
Total Cost Per Month		\$504.91

To view a summary of the total charges including AWS Data Transfer Out and the Free Usage Tier discounts, move on to [Summing It All Up \(p. 50\)](#) .

Summing It All Up


To calculate the total cost for this example, we add the cost for Amazon EC2 instances and the AWS Data Transfer Out and then subtract any discount that falls into the AWS free usage tier. To learn more about the free usage tier and to find out if you are eligible, go to [Getting Started with AWS Free Usage Tier](#).

The total AWS Transfer Out is an aggregate Data Transfer Out usage across all Amazon EC2 instances. For Amazon EC2, we have 0.05 GB per day, which is approximately 1.525 GB per month. Because up to 1 GB per month of data transferred out is free, we are left with a total of 0.525 GB per month.

**Getting Started with AWS Computing Basics for
Windows
How to Further Save Costs**

Variable	Formula	Calculation
AWS Data Transfer	(Data in (GB) X Data In Rate) + (Data out (GB) X Data Out Rate) ----- -----	0.1525 X \$0.00 + (0.525) X \$0.12 ----- \$0.06

The following image from the calculator shows an example of your monthly estimate.



According to the calculator, the total cost for Amazon EC2 is \$481.57.

How to Further Save Costs

In the example deployment we have been discussing, we used On-Demand Instances for all six of our instances. With On-Demand Instances, you are charged only from the time you launch an instance until the time you terminate it. If you plan to be running your instances for a long time, you can save more money by reserving them.

To obtain Reserved Instances, you make a low, one-time payment for each instance you want to reserve. In return, you receive a significant discount on the hourly usage charge. If you know approximately how heavily your Amazon EC2 instances will be used when they are running, you can save even more by opting for Heavy, Medium, or Light Utilization Reserved Instances. With Heavy Utilization, you pay a higher upfront fee, but your hourly usage rate is the lower than that for Medium and Light Utilization Reserved Instances. Light Utilization has the lowest upfront free, but your hourly rate is higher than that for Medium and Heavy Utilization Instances. In the previous example, three of the instances are running all the time. This is an ideal candidate for Heavy Utilization Reserved Instances. Two instances run only during peak traffic, about one third of the time. These instances are ideal candidates for Light Utilization

Getting Started with AWS Computing Basics for Windows

How to Further Save Costs

Reserved Instances. Because the instance that performs the nightly backups runs only a few hours a day, you can run it as an On-Demand Instance.

Reserved Instances can be obtained on 1-year or 3-year terms. The 3-year term can offer additional savings over the 1-year term. For more information about reserved instances, go to [Amazon EC2 Reserved Instances](#). You can see the cost comparison with On-Demand versus Reserved Instances over a three-year period in the following table.

Using the same characteristics and metrics in the above example, let's update the calculator to enter the Heavy and Light Utilization as in the following diagram.

Choose region: **US-East / US Standard (Northern Virginia)** Inbound Data Transfer is Free and Outbound Data Transfer is 1 GB free per region per month

Amazon Elastic Compute Cloud (Amazon EC2) is a web service that provides resizable compute capacity in the cloud. It is designed to make web-scale computing easier for developers. Amazon Elastic Block Store (EBS) provides persistent storage to Amazon EC2 instances. [Clear Form](#)

Compute: Amazon EC2 On-Demand Instances:

Description	Instances	Usage	Instance Type	Operating System	Tenancy	Detailed Monitoring
	1	3 Hours/Day	Micro <input type="checkbox"/> EBS-Optimized	Windows	Default	<input type="checkbox"/>

Compute: Amazon EC2 Reserved Instances:

Description	Instances	Usage	Instance Type	Operating System	Offering and Term	Tenancy	Detailed Monitoring
	3	24 Hours/Day	Small <input type="checkbox"/> EBS-Optimized	Windows	Heavy Utilization 3 yr term	Default	<input type="checkbox"/>
	2	8 Hours/Day	Small <input type="checkbox"/> EBS-Optimized	Windows	Light Utilization 3 yr term	Default	<input type="checkbox"/>

Storage: Amazon EBS Volumes:

Description	Volumes	Volume Type	Storage	IOPS	Snapshot Storage
	6	Standard	30 GB	100	0 GB-month of Storage

Elastic IP:

Number of Additional Elastic IPs:

Elastic IP Non-attached Time: Hours/Month

Number of Elastic IP Remaps: Per Month

Data Transfer:

Inter-Region Data Transfer Out: GB/Day

Data Transfer Out: GB/Day

Data Transfer In: GB/Month

Intra-Region Data Transfer: GB/Month

Public IP/Elastic IP Data Transfer: GB/Month

Elastic Load Balancing:

Number of Elastic LBs:

Total Data Processed by all ELBs: GB/Day

The total monthly cost is calculated the same way as the previous example, except that there is an additional one-time fee for Reserved Instances. The total cost is shown in the following diagram.

Getting Started with AWS Computing Basics for Windows

How to Further Save Costs

Services		Estimate of your Monthly Bill (\$ 270.27)	
Estimate of Your Monthly Bill			
<input checked="" type="checkbox"/> Show First Month's Bill (include all one-time fees, if any)			
With AWS, You only pay for what you use. Below you will see an estimate of your monthly bill. Expand each line item to see cost breakout of each service. To save this bill and input values, click on 'Save and Share' button. To remove the service from the estimate, click on the red cross.			
Save and Share			
<input type="checkbox"/> Amazon EC2 Service (US-East)			\$ 1406.21
Compute:	\$	99.19	
Intra-Region Data Transfer:	\$	0.00	
EBS Volumes:	\$	18.00	
EBS IOPS:	\$	158.11	
EBS Snapshots:	\$	0.00	
Reserved Instances (One-time Fee):	\$	1112.60	
Elastic IPs:	\$	0.00	
Elastic LBs:	\$	18.30	
Data Processed by Elastic LBs:	\$	0.01	
Dedicated Per Region Fee:	\$	0.00	
Inter-Region Data Transfer Out	\$	0.00	
<input type="checkbox"/> AWS Data Transfer In			\$ 0.00
<input type="checkbox"/> AWS Data Transfer Out			\$ 0.06
<input type="checkbox"/> AWS Support (Basic)			\$ 0.00
Free Tier Discount:			\$ -23.41
Total One-Time Payment:			\$ 1112.60
Total Monthly Payment:			\$ 270.27

The following table compares the total costs for using a mix of Heavy and Light Utilization Reserved Instances with those for On-Demand Instances.

Instance	Monthly Cost	One-time Fee	Total Cost (3 years)
6 On-Demand Instances	\$481.57	n/a	\$17336.52
1 On-Demand Instance 3 Heavy Utilization Reserved Instances 2 Light Utilization Reserved Instances	\$270.27	\$1112.60	\$10842.32

As you can see from the table, by using a mix of Heavy and Light Utilization Reserved Instances in this example, you can save approximately 32%. For more information on how AWS pricing works, go to the [How AWS Pricing Works](#) whitepaper.

Another way you can save money is by using Spot Instances. Spot Instances are unused Amazon EC2 capacity that you bid for. Instances are charged at the Spot Price, which is set by Amazon EC2 and fluctuates periodically depending on the supply of, and demand for, Spot Instance capacity. If your maximum bid exceeds the current Spot Price, your bid request is fulfilled, and your instances will run until either you choose to terminate them or the Spot Price increases above your maximum bid, whichever is sooner. To learn more about Spot Instances, go to <http://aws.amazon.com/ec2/spot-instances>.

Related Resources

The following table lists related resources that you'll find useful as you work with AWS services.

Resource	Description
AWS Products and Services	A comprehensive list of products and services AWS offers.
Documentation	Official documentation for each AWS product including service introductions, service features, and API references, and other useful information.
AWS Architecture Center	Provides the necessary guidance and best practices to build highly scalable and reliable applications in the AWS cloud. These resources help you understand the AWS platform, its services and features. They also provide architectural guidance for design and implementation of systems that run on the AWS infrastructure.
AWS Economics Center	Provides access to information, tools, and resources to compare the costs of Amazon Web Services with IT infrastructure alternatives.
AWS Cloud Computing Whitepapers	Features a comprehensive list of technical AWS whitepapers covering topics such as architecture, security, and economics. These whitepapers have been authored either by the Amazon team or by AWS customers or solution providers.
Videos and Webinars	Previously recorded webinars and videos about products, architecture, security, and more.
Discussion Forums	A community-based forum for developers to discuss technical questions related to Amazon Web Services.
AWS Support Center	The home page for AWS Technical Support, including access to our Developer Forums, Technical FAQs, Service Status page, and AWS Premium Support. (subscription required).
AWS Premium Support Information	The primary web page for information about AWS Premium Support, a one-on-one, fast-response support channel to help you build and run applications on AWS Infrastructure Services.

Resource	Description
Form for questions related to your AWS account: Contact Us	This form is <i>only</i> for account questions. For technical questions, use the Discussion Forums.
Conditions of Use	Detailed information about the copyright and trademark usage at Amazon.com and other topics.

Document History

This document history is associated with the release of Getting Started with AWS Computing Basics for Windows. This guide was last updated on May 06, 2014.

Change	Description	Release Date
New content	Created new document	29 February 2012